# ginga Documentation

Release 3.1.0

**Ginga Maintainers** 

Jul 20, 2020

## CONTENTS

I About Ginga	1
II Copyright and License	5
III Requirements and Supported Platforms	9
IV Getting the Source	13
V Building and Installation	17
1 Installation	21
VI Documentation	27
2 What's New	29
3 Quick Reference	41
4 User's Manual	49
5 Developer's Manual	133
6 Optimizing Performance	177
7 FAQs	179
8 Reference/API	183

VII Bug Reports	239
VIII Developer Info	243
IX Etymology	247
X Pronunciation	251
Python Module Index	255
Index	257

## Part I

# **About Ginga**

Ginga is a toolkit designed for building viewers for scientific image data in Python, visualizing 2D pixel data in NumPy arrays. It can view astronomical data such as contained in files based on the FITS (Flexible Image Transport System) file format. It is written and is maintained by software engineers at the National Astronomical Observatory of Japan, the Space Telescope Science Institute, and other contributing entities.

The Ginga toolkit centers around an image display class which supports zooming and panning, color and intensity mapping, a choice of several automatic cut levels algorithms and canvases for plotting scalable geometric forms. In addition to this widget, a general purpose "reference" FITS viewer is provided, based on a plugin framework.

A fairly complete set of "standard" plugins are provided for features that we expect from a modern FITS viewer: panning and zooming windows, star catalog access, cuts, star pick/FWHM, thumbnails, etc.

## Part II

# **Copyright and License**

Copyright (c) 2011-2020 Ginga Maintainers. All rights reserved.

Ginga is distributed under an open-source BSD licence. Please see the file LICENSE.txt in the top-level directory for details.

## Part III

# **Requirements and Supported Platforms**

Because Ginga is written in pure Python, it can run on any platform that has the required Python modules and has a supported widget set. The basic Ginga display class supports the Qt (4 and 5), PySide, Gtk (2 and 3), Tk widget sets natively as well as any Matplotlib Figure, and HTML5 canvases in a web browser. The full reference viewer supports Qt and Gtk variants. Ginga can also be used in Jupyter notebooks.

## Part IV

# **Getting the Source**

Clone from Github:

git clone https://github.com/ejeschke/ginga.git

To get a ZIP file or tarball instead, see the links on About Ginga.

## Part V

# **Building and Installation**

#### Download and install from pip:

pip install ginga

#### Or conda:

```
conda install ginga -c conda-forge
```

The reference viewer can then be run using the command ginga.

For detailed instructions, see:

#### CHAPTER

## ONE

## INSTALLATION

### **1.1 Dependencies**

Ginga is written entirely in Python, and only uses supporting Python packages. There is nothing to compile (unless you need to compile one of the supporting packages).

In recent Linux, Mac, and Windows versions, all of the packages are available in binary (installable) form. It should not be necessary to compile anything, but as always, your mileage may vary.

#### 1.1.1 REQUIRED

- python (v. 3.5 or higher)
- setuptools-scm
- numpy (v. 1.13 or higher)
- astropy

Highly recommended, because some features will not be available without it:

- scipy
- pillow
- opency-python (also distributed as opency or python-opency, depending on where you get it from)
- piexif
- beautifulsoup4
- docutils (to display help for plugins)

For opening FITS files you will need one of the following packages:

- astropy
- fitsio

For WCS resolution you will need one of the following packages:

- astropy
- kapteyn
- astLib
- starlink

#### 1.1.2 BACKENDS (one or more)

Ginga can draw its output to a number of different back ends. Depending on which GUI toolkit you prefer (and what you want to do), you will need at least one of the following:

- QtPy (PyQt4 or PyQt5)
- PySide (Qt4/Qt5 alternative)
- pygobject (gi) AND pycairo (GTK 3)
- tkinter
- matplotlib
- tornado
- aggdraw
- Pillow (PIL fork)

#### 1.1.3 RECOMMENDED

Certain plugins in the reference viewer (or features of those plugins) will not work without the following packages:

- matplotlib (required by: Pick, Cuts, Histogram, LineProfile)
- scipy (required by: Pick, some built-in auto cuts algorithms used when you load an image)

#### To save a movie:

• mencoder (command line tool required by: Cuts)

Helpful, but not necessary (may optimize or speed up certain operations):

- opency-python (speeds up rotation, mosaicing and some transformations)
- pyopencl (speeds up rotation, mosaicing and some transformations)
- pyopengl (for using OpenGL features)
- numexpr (speeds up rotation a little)
- filemagic (aids in identifying files when opening them)
- Pillow (useful for various RGB file manipulations)

## **1.2 Notes on Supported Widget Sets**

In the discussion below, we differentiate between the Ginga viewing widget, such as used in the examples/\\*/ example\\*.py programs and the full reference viewer, which includes many plugins (ginga).

**Note:** For the full reference viewer, Mac and Windows users should probably install the Qt version, unless you are the tinkering sort. Linux can use either Qt or GTK fine.

#### 1.2.1 Qt/PySide

Ginga can use either PyQt or PySide, version 4 or 5. It will auto-detect which one is installed, using the qtpy compatibility package. There is support for both the basic widget and the full reference viewer.

**Note:** If you have both installed and you want to use a specific one then set the environment variable QT\_API to either "pyqt" or "pyside". This is the same procedure as for Matplotlib.

#### 1.2.2 GTK

Ginga can use GTK 3 (with gi). (If you have an older version of pycairo package, you may need to install a newer version from pycairo).

#### 1.2.3 Tk

Ginga's Tk support is limited to the viewing widget itself. For overplotting (graphics) support, you will also need:

- Pillow
- · opency-python
- aggdraw

#### 1.2.4 Matplotlib

Ginga can render directly into a Matplotlib figure. Support is limited to the viewing widget itself. Any of the backends that Matplotlib supports is usable. Performance is not as good as to one of the "native" backends listed above, but oh, the overplot options!

#### 1.2.5 HTML5 web browser

Ginga can render into an HTML5 canvas via a web server. Support is limited to the viewing widget itself. See the notes in examples/pg/example2\_pg.py. Tested browsers include Chromium (Chrome), Firefox, and Safari.

### **1.3 Basic Installation**

You can download and install via pip by choosing the command that best suits your needs (full selection is defined in setup configuration file):

```
pip install ginga # The most basic installation
pip install ginga[recommended,qt5] # Qt5
pip install ginga[recommended,gtk3] # GTK 3
```

Or via conda:

conda install ginga -c conda-forge

The reference viewer can then be run using the command ginga.

## **1.4 Installation from Source**

1. Clone from Github:

git clone https://github.com/ejeschke/ginga.git

Or see links on this page to get a ZIP file or tarball.

2. Unpack, go into the top level directory, and run:

```
pip install -e .
```

## **1.5 Platform Specific Instructions**

#### 1.5.1 Linux (Debian/Ubuntu)

If you are on a relatively recent version of Debian or Ubuntu, something like the following will work:

apt install python3-ginga

If you are using another distribution of Linux, we recommend to install via Anaconda or Miniconda as described below.

#### 1.5.2 Mac/Windows/Linux (others)

#### Anaconda

For Mac/Windows or other Linux users, we recommend installing the Anaconda distribution (or Miniconda). This distribution already includes all of the necessary packages to run Ginga.

After installing Anaconda, open the Anaconda Prompt and follow instructions under Basic Installation via conda.

## 1.6 Running tests

1. Install the following packages:

\$ pip install -e .[test]

2. Run the tests using pytest:

\$ pytest

## 1.7 Building documentation

1. Install the following packages:

\$ pip install -e .[docs]

2. Build the documentation using make:

\$ cd doc
\$ make html

## Part VI

## Documentation

#### CHAPTER

#### TWO

## WHAT'S NEW

### 2.1 Ver 3.1.0 (2020-07-20)

- Zoom and Pan plugins refactored. Now shows graphical overlays.
- Improved performance of rendering when flipping, swapping axes or rotating viewer.
- Fixed a bug where the display was not redrawn if an ICC profile was changed
- · Fixed bugs relating to drawing XRange, YRange and Rectangle objects on rotated canvas
- Fixed a bug with fit image to window (zoom\_fit) which was off by half a pixel
- Fixed an issue where an error message appears in the log if the scale is so small the image is invisible
- Fixed an issue where the readout under the cursor for value is reported for an empty row to the left and column below of pixels
- Removed dependence on astropy-helpers submodule.
- Fixed an issue where limits were not reset correctly if image being viewed is modified in place (and data array changes size)
- Fixed an issue with Mosaic plugin where images with a PC matrix were not always oriented correctly
- · New Collage plugin offers an efficient alternative way to view mosaics
- Fix for a bug where using Zoom and PixTable at the same time can cause wrong results to be displayed in PixTable
- New ability to specify alternative Ginga home directories, with custom layouts and plugin configurations (-basedir option)
- Fix for a bug that caused a crash when closing the Help window with Qt/PySide backend

### 2.2 Ver 3.0.0 (2019-09-20)

- Dropped Python 2 support. Ginga now requires Python 3.5 or later.
- Fixed an issue with some RGB images being viewed flipped
- Improved accuracy of Qt-based timers
- Pick plugin enhanced with option to center on found object; also default shape changed to a box rather than a rectangle
- Added support for ASDF and GWCS.

- Fixed drag-and-drop functionality in FBrowser plugin on Windows.
- Enabled HDU sorting via config file in MultiDim.
- Fixed a bug where display would get corrupted when adjusting interactive cuts or contrast on rotated image
- Improved smoothness and updates of Zoom plugin image
- · Improved smoothness and updates when rotating or shifting color map
- Fixed broken banner
- Improved pip installation commands for different backends.
- Fixed a bug where identically named HDUs could not be loaded by MultiDim
- · Fixed a bug where compressed HDUs could not be loaded by MultiDim
- · Plugins with splitter type panels now remember their sizes when closed
- LineProfile plugin's default Y-axis label is now "Signal", to be more scientifically accurate.
- Simplified plugins Colorbar, Contents, Cursor, Errors, Header, Info, Log, Pan, and Thumbs plugins. Made all of these restartable. Subclasses of these plugins may require refactoring in a couple of cases.
- Selecting item in FBrowser now populates its text box properly.
- Support opening all extensions of given extension name from a FITS file (e.g., filename.fits[SCI, \*]) from Ginga command line or FBrowser.
- New Downloads plugin for monitoring/managing URI downloads
- Supports PySide2 (alternative Qt5 backend)
- Added statistics line to Histogram plugin
- Removed support for gtk2, since it is not supported for Python 3
- new styles added for Point canvas type: circle, square, diamond, hexagon, uptriangle, downtriangle
- New file opener framework
- Text objects can be resized and rotated in edit mode on the canvas
- Added ellipse and box annulus types as Annulus2R canvas object
- Supports plotting DS9 regions via 2-way conversion between Ginga canvas types and Astropy regions

## 2.3 Ver 2.7.2 (2018-11-05)

- Fix for linewidth attribute in shapes for AGG backend
- Fix for ellipse rotation in OpenCv backend
- Better text rendering for OpenCv backend (loadable fonts)
- · enhancements to the Ruler plugin for reference viewer
- supports quick loading from astropy NDData (or subclassed) objects
- · Support for scaling fonts on high-dpi displays
- · Fixed a bug where adjusting autocuts parameters in Preferences would crash the Qt backend
- Fixed a bug that caused windows to disappear when changing workspace to MDI mode under Gtk3 backend
- · Fixed a bug where local plugins were not properly closed when a channel is deleted

- Fixed a bug in which the ColorMapPlugin canvas was not scaled to the correct size
- · Improvements to synchronous refresh feature to reduce jitter and increase frame rate
- Fix for navigating certain data cubes with MutltiDim plugin
- Added new percentage transform and coordinate mapper type (allow placement of objects as a percentage of the window size)
- Updates to Compass canvas type and Pan plugin
- Documentation improvements for writing plugins

## 2.4 Ver 2.7.1 (2018-07-09)

- Fix for image rendering bug which shows last row and column of image being drawn twice
- Added option to "Compass" draw type to be in pixels (X/Y) or wcs (N/E)
- Changed Pan plugin to attempt to draw both kinds of compasses
- Log plugin enhanced to show lines logged before it was opened
- Info plugin adds convenience controls for "Follow New" and "Raise New"
- WCSMatch plugin enhanced to offer fine grained control over sync
- fixed an issue in Debian build that caused long start up times
- User can dynamically add scrollbars to channel viewers in Preferences
- Made Gtk backend default to 'gtk3' "-t gtk" now invokes gtk3 instead of gtk2 choose "-t gtk2" if you want the gtk2 back end
- · Fixed a bug with opening wildcard-type filespec from the command line
- Fixed an issue in Thumbs plugin with opening FITS tables from the command line
- Fixes for some keyboard focus (Gtk) and unintentional channel changes (Qt) when viewer is in MDI mode
- IRAF plugin moved to experimental folder
- Allow setting of initial channel list, local, global and disabled plugins from general configuration file
- Fix for a bug when using OpenCv acceleration on dtype('>f8') arrays
- · Fixed a bug where colormap scale markers were sometimes not spaced wide enough
- Workaround for failed PDF build in RTD documentation

### 2.5 Ver 2.7.0 (2018-02-02)

- Fix for gtk 4.0 (use "gtk3" backend, it works for 4.0)
- · Fix for broken polygon containment test
- Addition of configurable zoom handlers for pan gestures
- Fix for some broken tests under python 2.7
- Update to mode handling via keyboard shortcuts
  - addition of a new "meta" mode used primarily for mode switching

- most modes now initiated from meta mode, which frees up keys for other uses
- see Ginga quick reference for details on how the new bindings work
- Efficiency update for Thumbs plugin when many thumbs are present
- Default for the save\_layout option is now True, so the reference viewer will write out its layout state on exit and restore it on startup. See documentation in the "customization" section of the manual.
- Plugins can now be organized by category and these categories are used to construct a hierarchical Operations menu
- · Zoom and Header plugins are now not started by default
- Fix for "sortable" checkbox behavior on Header plugin
- Default keyboard mode type is now 'locked' (prev 'oneshot')
- · Fixes for missing CSS file in installation script
- Less confusing behavior for workspace and toolbar arrow buttons

## 2.6 Ver 2.6.6 (2017-11-02)

- Fix for broken sorting in Contents plugin in gtk backends
- Fix for resize bug in switching in and out of grid view in gtk backends
- Updated to have efficient support for gtk3
  - please install compatible pycairo from github.com/pygobject/pycairo if you get a "Not implemented yet" exception bubbling up from a method called cairo.ImageSurface.create\_for\_data()
- Addition of a "Quick Mode" to the Pick plugin-see documentation
- More consistent font handing between widgets and Ginga canvases
- Bug fix for importing some types of matplotlib color maps
- Add antialiasing for Qt back end
- · Bug fixes and enhancements for Qt gestures holding shift with pinch now keeps position under cursor
- New Jupyter notebooks back end based on ipywidgets requirements: \$ pip install ipyevents see examples/jupyter-notebook/
- Fixes to various reference viewer plugins

## 2.7 Ver 2.6.5 (2017-07-31)

- · Coordinate transforms refactored for speed and code clarity
- Some canvas shapes refactored for better code reuse
- Allow max and min scale limits to be disabled (by None)
- · Fixed a bug that prevented the reference viewer from resizing correctly with Qt back end
- · Refactored WCS wrapper module for code clarity
- Set minimum astropy version requirement to 1.X
- Fixed a bug in NAXIS selection GUI (MultiDim plugin)

- · Fixed MDI window resizing with Gtk back ends
- Fixed an error where zoom 100% button did not correctly zoom to 1:1 scale
- Several fixes for astropy 2.0 compatibility
- Fixed a bug in the FBrowser plugin when channel displaying a table and attempting to load a new file
- · Fixed a bug when setting the pan position manually by wcs coordinates
- Updates for changes in PIL.ImageCms module
- · Fix for window corruption on certain expose events
- · New default bindings for touch pads and differentiation from wheel zoom

# 2.8 Ver 2.6.4 (2017-06-07)

- Added new ScreenShot plugin to take PNG/JPEG snaps of the viewer window
- Enhancements to the Pick plugin
  - Added ability to make shapes besides rectangles for enclosing pick area. Masks out unwanted pixels. Choose the shape in the Settings tab.
  - Changed behavior of pick log to only write the log when the user clicks the save button.
  - Changed the name of the save button to "Save as FITS table" to make it clear what is being written.
  - If "Show candidates" is selected in Settings, then ALL of the candidates are saved to the log.
  - Added documentation to the manual
  - Bug fix for error when changing radius
- Improvements to layout of Operations menu (plugin categories)
- Colorbar scale now placed below the color wedge and is more legible
- Bug fixes for LineProfile plugin
- Slit function for Cuts plugin can be enabled from GUI
- Bug fixes for Slit function
- Info plugin can now control new image cut/zoom/center settings
- Fixed an issue with the MultiDim plugin that could result in a hang with some back ends
- New canvas type for displaying WCS grid overlay and new WCSAxes plugin that uses it
- · Bug fixes to scrolling via scrollbars and vert/horiz percentages
- Enhancements to the LineProfile plugin
  - several new shapes besides the standard point
  - plot multiple lines

## 2.9 Ver 2.6.3 (2017-03-30)

- Fix for issue that stops ginga startup when loading externally distributed plugins that have errors
- Fix for an issue loading plugins from the command line when they are nested in a package
- Added bindings for moving +/- pixel delta in X or Y and centering on the pixel
- · Fixes for some key mappings for tk, matplotlib and HTML5 canvas backends
- Fixes for IRAF plugin under python 3
- Fix for a bug using remote control (RC) plugin from python2 client to python 3 ginga
- Documentation updates

## 2.10 Ver 2.6.2 (2017-02-16)

- Added some colormaps from ds9 that don't have equivalents in Ginga or matplotlib
- · Fix for recognizing CompImage HDU type when using astropy.io.fits
- Add new experimental OpenGL back end
- Fixes for Tk back end on python 3
- You can now write separately distributed and installable plugins for the reference viewer that Ginga will find and load on startup
- · Added -sep option to load command line files into separate channels
- New help screen feature available for plugins
- Lots of updates to documentation
- · Fixed a stability issue with drag and dropping large number of files under Linux
- · Fixes for python3 and several example programs
- Fix for interactive rotation bug under matplotlib back end

# 2.11 Ver 2.6.1 (2016-12-22)

- Added a working MDI workspace for gtk2/gtk3.
- Added scrollbar frames. See examples/qt/example1\_qt.py for standalone widget. Can be added to reference viewer by putting 'scrollbars = "on" in your channel\_Image.cfg preferences.
- Reorganized reference viewer files under "rv" folder.
- Improved Pick plugin: nicer contour plot, pick log uses table widget, pick log saved as a FITS table HDU
- Pick and Zoom plugins can now use a specific color map, rather than always using the same one as the channel window
- gtk3 reference viewer can now be resized smaller than the original layout (gtk2 still cannot)
- · added ability to save the reference viewer size, layout and position on screen
- gtk MDI windows now remember their size and location when toggling workspace types
- · Fixes for problems with pinch and scroll gestures with Qt5 backend

- Fixed a bug where scale changes between X and Y axes unexpectedly at extreme zoom levels
- Fixed a bug where cursor could get stuck on a pan cursor
- Added ability to define a cursor for any mode
- Added documented virtual methods to ImageView base class
- Added a workaround for a bug in early versions of Qt5 where excessive mouse motion events accumulate in the event queue

# 2.12 Ver 2.6.0 (2016-11-16)

With release 2.6.0 we are moving to a new versioning scheme that makes use of github tagged releases and a "dev" versioning scheme for updates between releases.

This release includes many bugfixes and improvements, new canvas types (XRange and YRange), a Command plugin, WCSMatch plugin, dynamically configurable workspaces, OpenCv acceleration, an HTML5 backend and much much more.

## 2.13 Ver 2.2.20160505170200

Ginga has merged the astropy-helpers template. This should make it more compatible management-wise with other astropy-affiliated packages.

## 2.14 Ver 2.2.20150203025858

Ginga drawing canvas objects now can specify points and radii in world coordinates degrees and sexigesimal notation.

- · default is still data coordinates
- can play with this from Drawing plugin in reference viewer

# 2.15 Ver 2.1.20141203011503

Major updates to the drawing features of ginga:

- new canvas types including ellipses, boxes, triangles, paths, images
- objects are editable: press 'b' to go into edit mode to select and manipulate objects graphically (NOTE: 'b' binding is considered experimental for now-editing interface is still evolving)
- editing: scale, rotate, move; change: fill, alpha transparency, etc.
- · editing features available in all versions of the widget
- updated Drawing plugin of reference viewer to make use of all this

# 2.16 Ver 2.0.20140905210415

Updates to the core display and bindings classes:

- improvements to interactive rotation command-now resume rotation from current value and direction is relative to horizontal motion of mouse
- most keyboard modes are now locking and not oneshot (press to turn on, press again (or hit escape) to turn off
- additional mouse button functionality in modes (see quick reference)
- some changes to default keyboard bindings (see quick reference)
- changes to auto cuts parameters always result in a new autocut being done (instead of having to explicitly perform the autocut)-users seem to expect this
- autocenter preference changed from True/False to on/override/off

Reference viewer only: new global plugin "Toolbar" provides GUI buttons for many operations that previously had only keyboard bindings

# 2.17 Ver 2.0.20140811184717

Codebase has been refactored to work with python3 via the "six" module. Tests can now be run with py.test as well as nosetest.

## 2.18 Ver 2.0.20140626204441

Support has been added for image overlays. It's now possible to overlay RGB images on top of the canvas. The images scale, transform and rotate wrt the canvas.

## 2.19 Ver 2.0.20140520035237

Auto cut levels algorithms have been updated. "zscale" has been reinforced by using the module from the "numdisplay" package, which does a fair sight closer to IRAF than the previous one Ginga was using. Also, the algorithm "median" (median filtering) makes a comeback. It's now fast enough to include and produces more usable results.

# 2.20 Ver 2.0.20140417032430

New interactive command to orient the image by WCS to North=Up. The default binding to 'o' creates left-handed orientation ('O' for right-handed). Added a command to rotate the image in 90 deg increments. Default binding to 'e' rotates by 90 deg ('E' for -90 deg).

# 2.21 Ver 2.0.20140412025038

Major update for scale (mapping) algorithms

The scale mapping algorithms (for mapping data values during rendering) havebeen completely refactored. They are now separated from the RGBMap class and are pluggable. Furthermore I have redone them modeled after the ds9 algorithms.

There are now eight algorithms available: linear, log, power, sqrt, squared, asinh, sinh, histeq. You can choose the mapping from the Preferences plugin or cycle through them using the binding to the 's' key (Use 'S' to reset to linear). There is also a mouse wheel mapping than can be assigned to this function if you customize your bindings. It is not enabled by default.

The Preferences plugin has been updated to make the function a little clearer, since there was some confusion also with the intensity map feature that is also part of the final color mapping process.

## 2.22 Ver 2.0.20140114070809

- The SAMP plugin has been updated to work with the new astropy.vo.samp module.
- The Catalogs plugin has been updated to allow the user to define the radius of the conesearch or image search by drawing a circle (as well as the previous option–a rectangle).

# 2.23 Ver 2.0.20131218034517

The user interface mapping just got a bit easier to use. Ginga now provides a way to do most UI remapping just by placing a simple config file in your ~/.ginga directory. An example for ds9 users is in the new "examples" folder.

Many simple examples were moved out of "scripts" and stored under subdirectories (by GUI toolkit) in "examples".

## 2.24 Ver 2.0.20131201230846

Ginga gets trackpad gestures! The Qt rendering class gets support for pinch and pan gestures:

- The pinch/rotate gesture works as expected on a Mac trackpad
- The pan gesture is not a two-finger pan but a "non-standard", Qt-specific one-finger pan. These are experimental for now, but are enabled by default in this release.

Also in this release there has been a lot of updates to the documentation. The developer and internals sections in particular have a lot of new material.

# 2.25 Ver 2.0.20131030190529

The great renaming

I really dislike it when developers do this, so it pains me to do it now, but I have performed a mass renaming of classes. FitsImage ended up being the View in the MVC way of doing things, yet it shared the same naming style as the model classes AstroImage and PythonImage. This would have been the source of endless confusion to developers down the road. Also, PythonImage needed to get renamed to something more akin to what it actually represents.

So the renaming went like this:

- FitsImage -> ImageView
- FitsImage{XYZ} -> ImageView{XYZ}
- PythonImage -> RGBImage

So we have:

- M: BaseImage, AstroImage, RGBImage
- V: ImageView{XYZ}
- C: Bindings, BindMap

I did this in the brand new 2.0 version so at least devs have a heads up that things will not be backward compatible.

And I apologize in advance for any renaming and support issues this may cause for you. Fire up your editor of choice and do a query/replace of "FitsImage" with "ImageView" and you should be good to go.

# 2.26 Ver 1.5-20131022230350

Ginga gets a Matplotlib backend!

Ginga can now render to any Matplotlib FigureCanvas. The performance using this backend is not as fast as the others, but it is acceptable and opens up huge opportunities for overplotting.

See scripts/example{1,2,3,4,5}\_mpl.py

Also merges in bug fixes for recent changes to astropy, and support for other python WCS packages such as kapteyn and astLib.

# 2.27 Ver 1.5-20130923184124

### 2.27.1 Efficiency improvements

Efforts to improve speed of entire rendering pipeline and widget specific redrawing

- Decent improvements, Ginga can now render HD video (no sound) at 30 FPS on older hardware (see scripts/example1\_video.py). This translates to a slightly speedier feel overall for many operations viewing regular scientific files.
- Fixed a bug that gave an error message of Callback.py:83 (make\_callback) | Error making callback 'field-info': 'Readout' object has no attribute 'fitsimage'
- Version bump

# 2.28 Ver 1.4.20130718005402

### 2.28.1 New Agg backend

There is now an Agg rendering version of the ImageView object.

- uses the python "aggdraw" module for drawing; get it here -> https://github.com/ejeschke/aggdraw
- this will make it easy to support all kinds of surfaces because the graphics drawing code does not have to be replicated for each toolkit
- see example code in /scripts/example1\_agg\_gtk.py
- currently not needed for Gtk, Qt versions of the object

## 2.28.2 New Tk backend

There is now a Tk rendering version of the ImageView object.

- see ginga.tkw.ImageViewTk
- renders on a Tk canvas
- see example code in /scripts/example{1,2}\_tk.py
- you will need the aggdraw module (see above) to use it

## 2.28.3 AutoCuts

- the ginga.AutoCuts module has been refactored into individual classes for each algorithm
- The Preferences plugin for ginga now exposes all of the parameters used for each cut levels algorithm and will save them

## 2.28.4 Etc

- additions to the manual (still incomplete, but coming along)
- lots of docstrings for methods added (sphinx API doc coming)
- · many colors added to the color drawing example programs
- WhatsNew.txt file added

### CHAPTER

## THREE

## **QUICK REFERENCE**

## 3.1 Main image window

These keyboard and mouse operations are available when the main image window has the focus.

### 3.1.1 Mode control commands

#### About modes

Certain keystrokes invoke a *mode*—modes are usually indicated by the *mode indicator*: a small black rectangle with the mode name in one corner of the view. In a mode, there are usually some special key, cursor, and scroll bindings that override *some* of the default ones.

Modes additionally have a *mode type* which can be set to one of the following:

- held: mode is active while the activating key is held down
- oneshot: mode is released by initiating and finishing a cursor drag or when Esc is pressed, if no cursor drag is performed
- locked: mode is locked until the mode key is pressed again (or Esc)
- softlock: mode is locked until another mode key is pressed (or Esc)

By default, most modes are activated in "oneshot" type, unless the mode lock is toggled. The mode type is indicated in the brackets after the mode name in the mode indicator. The following keys are important for initiating a mode:

Commmand	Description
Space	Enter "meta" mode. Next keystroke will trigger a particular mode.
Esc	Exit any mode. Does not toggle the lock.
1	Toggle the soft lock to the current mode or any future modes.
L	Toggle the normal lock to the current mode or any future modes.

#### "meta" mode

Most modes are defined so that they are invoked from a special intermediate mode called "meta". In that case a twokey sequence is required to enter the mode: pressing the key that invokes "meta" and then pressing the key that invokes the desired mode. The following table shows the modes that can be triggered from meta mode.

Command	Description
Space	Exit/Enter "meta" mode.
b	Enter draw mode (canvas must be enabled to draw).
q	Enter pan mode.
W	Enter freepan mode.
r	Enter rotate mode.
t	Enter contrast mode.
У	Enter cmap (color map) mode.
S	Enter cuts mode.
d	Enter dist (distribution) mode.

**Note:** For modes initiated from meta mode, the locked and softlock mode types work the same way, which is slightly different from that described above: you press the meta mode key to switch back to meta mode, from which you can enter another mode by pressing its key. You can always press Esc in any mode (including meta mode) to exit the mode.

### 3.1.2 Panning and zooming commands

Commmand	Description
Scroll wheel turned	Zoom in or out.
Shift + scroll wheel	Zoom while keeping location under the cursor.
Ctrl + scroll wheel turned	Pan in direction of scroll.
Digit (1234567890)	Zoom image to zoom steps 1, 2,, 9, 10.
Shift + Digit	Zoom image to zoom steps -1, -2,, -9, -10.
Backquote (`)	Zoom image to fit window and center it.
Minus, Underscore (-, _)	Zoom out.
Equals, Plus (=, +)	Zoom in.
Middle (scroll) button click	Set pan position (under cursor).
p	Set pan position (under cursor) for zooming.
Shift + left-click	Set pan position for zooming.
Shift + arrow key	Move pan position 1 pixel in that direction.
с	Set pan position to the center of the image.
q	Enter Pan mode.
W	Free Freepan mode.
Ctrl + left-drag	Proportional pan (press and drag left mouse button.
slash (/)	Set autocenter for new images to override.
question (?)	Toggle autocenter for images to on or off.
apostrophe (')	Set autozoom for new images to override.
double quote (")	Toggle autozoom for new images to on or off.

Commmand	Description
a	Auto cut levels.
d	Enter Color Distribution ("dist") mode. See Dist mode.
D	Reset color distribution algorithm to "linear".
S	Enter Cuts mode.
t	Enter Contrast mode.
Т	Restore the contrast (via colormap) to its original (unstretched, unshifted) state.
У	Enter <i>CMap</i> (color map) mode.
Y	Restore the color map to default (gray).
Ι	Invert the color map.
semicolon (;)	Set autocuts for new images to override.
colon (:)	Toggle autocuts for new images to on or off.

## 3.1.3 Cut levels and colormap commands

## 3.1.4 Transform commands

Commmand	Description
Left bracket ([)	Toggle flip image in X.
Left brace ({)	Reset to no flip of image in X.
Right bracket (])	Toggle flip image in Y.
Right brace (})	Reset to no flip image in Y.
Backslash (\)	Swap X and Y axes.
Vertical bar (I)	Reset to no swap of X and Y axes.
r	Enter Rotate mode.
R	Restore rotation to 0 degrees and additionally undo any flip/swap transformations.
period (.)	Increment current rotation by 90 degrees.
comma (,)	Decrement current rotation by 90 degrees.
0	Orient image by transforms and rotation so that WCS indicates North=Up and East=Left.
0	Orient image by transforms and rotation so that WCS indicates North=Up and East=Right.

## 3.1.5 Pan mode

Commmand	Description
left-drag	Pan proportionally to drag.
middle-click	Set pan position.
right-drag	Zoom in/out proportionally to L/R drag.
<modifier> + arrow key</modifier>	Pan in direction of arrow key. Adding Ctrl reduces amount, adding Shift reduces more.
р	Pan to position under cursor.
Z	Save current scale (see below for use).
backquote (`)	Zoom to fit window and center.
1	Pan to cursor and zoom to saved scale level (or 1:1 if no scale level saved).
с	Set pan position to the center of the image.
slash (/)	Set autocenter for new images to override.
question (?)	Toggle autocenter for images to on or off.
apostrophe (')	Set autozoom for new images to override.
double quote (")	Toggle autozoom for new images to on or off.

## 3.1.6 Freepan mode

Command	Description
Turn scroll wheel	Zoom while keeping location under the cursor.
left-click	Set pan position, zoom in a step and warp cursor to pan position (if supported on
	backend).
right-click	Set pan position, zoom out a step and warp cursor to pan position (if supported on
	backend).
middle-drag	Pans freely over entire image in proportion to cursor position versus window.
p, z, backquote, 1, c, arrow	(Same as for <i>Pan mode</i> .)
keys	

## 3.1.7 Dist mode

Commmand	Description
scroll	Select distribution from linear, log, etc.
b, up-arrow	Select prev distribution in list.
n, down-arrow	Select next distribution in list.
D	Reset color distribution algorithm to "linear".

## 3.1.8 Cuts mode

Command	Description
left-drag	Interactive cut <i>both</i> low and high levels (vertical cuts low, horizontal cuts high).
Ctrl + left-drag	Interactive cut low level only (horizontal drag).
Shift + left-drag	Interactive cut high level only (horizontal drag).
scroll	Coarse (10%) adjustment in/out.
Ctrl + scroll	Fine (1%) adjustment in/out.
a, right-click	Do an auto level to restore cuts.
S	Set cuts to min/max values.
А	Set cuts to 0/255 values (for 8bpp RGB images).
b, up-arrow	Select prev auto cuts algorithm in list.
n, down-arrow	Select next auto cuts algorithm in list.
semicolon (;)	Set autocuts for new images to override.
colon (:)	Toggle autocuts for new images to on or off.

## 3.1.9 Contrast mode

Comm-	Description	
mand		
left-drag	Interactive shift/stretch colormap (AKA contrast and bias). L/R controls shift, U/D controls stretch.	
right-click	Restore the contrast (via colormap) to its original (unstretched, unshifted) state.	
Т	Restore the contrast (via colormap) to its original (unstretched, unshifted) state.	

### 3.1.10 Rotate mode

Commmand	Description
left-drag	Drag around center of window to rotate image.
right-click	Restore rotation to 0 degrees (does not reset any flip/swap transformations).
R	Restore rotation to 0 degrees and additionally undo any flip/swap transformations.
Left bracket ([)	Toggle flip image in X.
Left brace ({)	Reset to no flip of image in X.
Right bracket (])	Toggle flip image in Y.
Right brace (})	Reset to no flip image in Y.
Backslash (\)	Swap X and Y axes.
Vertical bar (I)	Reset to no swap of X and Y axes.
period (.)	Increment current rotation by 90 degrees.
comma (,)	Decrement current rotation by 90 degrees.
0	Orient image by transforms and rotation so that WCS indicates North=Up and East=Left.
0	Orient image by transforms and rotation so that WCS indicates North=Up and East=Right.

### 3.1.11 Cmap mode

Commmand	Description
scroll	Select color map.
left-drag	Rotate color map.
right-click	Unrotate color map.
b, up-arrow	Select prev color map in list.
n, down-arrow	Select next color map in list.
Ι	Toggle invert color map.
r	Restore color map to unrotated, uninverted state.
Ctrl + scroll	Select intensity map.
j, left-arrow	Select prev intensity map in list.
k, right-arrow	Select next intensity map in list.
i	Restore intensity map to "ramp".
с	Toggle a color bar overlay on the image.
Y	Restore the color map to default ('gray').

## 3.1.12 Autozoom setting

The "autozoom" setting can be set to one of the following: "on", "override", "once" or "off". This affects the behavior of the viewer when changing to a new image (when done in the typical way) as follows:

- on: the image will be scaled to fit the window
- override: like on, except that once the zoom/scale is changed by the user manually it turns the setting to off
- once: like on, except that the setting is turned to off after the first image
- off: an image scaled to the current viewer setting

(In the *Reference Viewer*, this is set under the "Zoom New" setting in the channel preferences.)

## 3.1.13 Autocenter setting

The "autocenter" setting can be set to one of the following: "on", "override", "once" or "off". This affects the behavior of the viewer when changing to a new image (when done in the typical way) as follows:

- on: the pan position will be set to the center of the image
- override: like on, except that once the pan position is changed by the user manually it turns the setting to off
- once: like on, except that the setting is turned to off after the first image
- off: the pan position is taken from the current viewer setting

(In the *Reference Viewer*, this is set under the "Center New" setting in the channel preferences.)

## 3.1.14 Autocuts setting

The "autocuts" setting can be set to one of following: "on", "override", "once" or "off". This affects the behavior of the viewer when changing to a new image (when done in the typical way) as follows:

- on: the cut levels for the image will be calculated and set according to the autocuts algorithm setting
- override: like on, except that once the cut levels are changed by the user manually it turns the setting to off
- once: like on, except that the setting is turned to off after the first image
- off: the cut levels are applied from the current viewer setting

(In the ref:Reference Viewer, this is set under the "Cut New" setting in the channel preferences.)

### 3.1.15 Reference Viewer Only

Command	Description
Н	Raise Header tab.
Ζ	Raise Zoom tab.
D	Raise <b>Dialogs</b> tab.
С	Raise <b>Contents</b> tab.
less than (<)	Toggle collapse left pane.
greater than (>)	Toggle collapse right pane.
f	Toggle full screen.
F	Panoramic full screen.
m	Maximize window.
J	Cycle workspace type (tabs/mdi/stack/grid). Note that "mdi" type is not supported on all
	platforms.
k	Add a channel with a generic name.
Left, Right (arrow	Previous/Next channel.
keys)	
Up, Down (arrow	Previous/Next image in channel.
keys)	

**Note:** If there are one or more plugins active, additional mouse or keyboard bindings may be present. In general, the left mouse button is used to select, pick or move, and the right mouse button is used to draw a shape for the operation.

On the Mac, Ctrl + mouse button can also be used to draw or right-click. You can also invoke draw mode as described above in the section on modes.

### CHAPTER

## FOUR

# **USER'S MANUAL**

NN

Ginga is a toolkit for building viewers for scientific data in Python, particularly astronomical data. It also includes a reference viewer for viewing FITS (Flexible Image Transport System) files.

The Ginga viewer is based on an image display widget that supports:

- Zooming and panning
- Color and intensity mapping
- · A choice of several automatic cut levels algorithms, and
- Canvases for plotting scalable geometric forms.

In addition to the image display widget, the Ginga viewer provides a flexible plugin framework for extending the viewer with many different features.

A relatively complete set of standard plugins is provided for features that we expect from a modern viewer: panning and zooming windows, star catalog access, cuts, star pick/fwhm, and thumbnails.

# 4.1 Introduction

### 4.1.1 About

Ginga is a toolkit designed for building viewers for scientific image data in Python, visualizing 2D pixel data in numpy arrays. The Ginga toolkit can view astronomical data such as contained in files based on the FITS (Flexible Image Transport System) file format.

The Ginga toolkit is written and maintained by software engineers at the Subaru Telescope, National Astronomical Observatory of Japan. The code is released as open-source under a BSD license and maintained at http://ejeschke.github.io/ginga/

### 4.1.2 Features

The Ginga toolkit centers around an image display widget that supports zooming and panning, color and intensity mapping, a choice of several automatic cut levels algorithms, and canvases for plotting scalable geometric forms.

In addition to this widget, a general purpose reference FITS viewer is provided, based on a plugin framework. A relatively complete set of standard plugins are provided for features that we expect from a modern FITS viewer: panning and zooming windows, star catalog access, cuts, star pick/fwhm, thumbnails, etc.

# 4.2 Core Concepts


The Ginga reference viewer operation is organized around several basic concepts: *workspaces*, *channels*, *plugins*, *modes*. Understanding these will greatly aid in using and modifying Ginga.

## 4.2.1 Workspaces

Ginga has a flexible workspace layout algorithm that allows customizing the appearance of the program. The majority of the Ginga interface is constructed as hierarchical series of horizontally or vertically-adjustable panels. Each panel is eventually a *workspace*. Each workspace is implemented by a GUI toolkit container widget such as a notebook widget, where each item in the workspace is identified by a tab.

However, workspaces can also take the form of a stack (like a tabbed widget but with no tabs showing), or a Multiple Document Interface (MDI) style container (subwindow desktop-style layout), or a grid layout.

Workspaces typically contain either a channel *viewer*, a *plugin* UI or another workspace. In its default configuration, Ginga starts up with a single row (horizontal) panel of three workspaces, as shown in the image below.



The panel is sandwiched vertically between a menu bar and a status bar. The left workspace is further subdivided into an upper and lower, and there are also thin horizontal workspaces below the central workspace. The central workspace is mainly used for viewers, while the other workspaces hold the plugin UIs.

The initial layout of the workspaces is controlled by a table in the Ginga startup script (see *Customizing Ginga*). By changing this table the layout can be substantially altered.

**Note:** Note that workspaces may be implemented by several types of container widgets such as fixed position subwindows, sliding panes, MDI-style subwindows, etc.


A notebook widget is simply the most common (default) case.

Some workspaces can be converted dynamically between the different types. If the workspace contains a *workspace toolbar*, the workspace type selector can be used to change the type:



In the example shown below, we show a cutout of the main workspace (tabbed), which has two tabs: a channel viewer (*Image*) and a second workspace (*ws1*).

The *ws1* workspace is configured as type *MDI* and has two windows: a viewer (*Image0*) and a third workspace (*ws2*). The third workspace contains a grid of four viewers. Depending on the the support of the back end widget set, tabs can be dragged between workspaces (or out onto the desktop if you are using the Gtk widget set), forming a new, detached workspace.



### 4.2.2 Channels

Another core tenet of Ginga is that that image content is organized into *channels*. A channel can be thought of as simply a named category under which similar types of images might be organized. A few examples are:

- A channel for each type of instrument at a telescope
- A channel for each observation or calibration target
- · Channels based on time or program or proposal identifier

If no channels are specified when Ginga starts up it simply creates a default channel named *Image*. New channels can be created using the *Channel/Add channel* menu item. Pressing the + button in the workspace menu also adds a new channel using a default name.

A channel always has an image viewer associated with it, and may additionally have a table viewer. The viewer is what you see in the active window representing that channel.



In the workspace toolbar, pressing – removes the currently selected channel, while pressing the up or down arrows moves between images in the selected channel.

In the case where multiple channels are present, they are usually visually organized as tabs, windows, and grid within the central workspace of the interface (as shown in the figure above) depending on how the workspace is configured. To change channels you simply click on the tab of the channel you want to view, or press the left or right arrow buttons in the workspace menu. There is also a channel selector in the plugin manager toolbar at the bottom of the center pane. You can change the channel by using the drop-down menu or by simply scrolling the mouse wheel on the control.

Zoom: 1.13x Cut Low: 1311									•					
Cut High: 2358										-				
Auto Levels	Cut Levels													
Cut New: override		138	1 1451	1521	1591	1661	1731	1801	1871	1941	2011	2081	2151	2221
Zoom New: on		α: <u>14:56</u> :(	)0.232 δ	5: +42:4	1:04.48	33 X:	1323.	470 Y:	2055.35	55 Valı	ue: 170	0		
Center New: off		HSC :	peration											
××× × * L	ا 🇭 🖏	▶ ▲ ♥	$\oplus \bigcirc$	1) 🔎	↔	<b>ð</b> 🗜	ł 🌾		\Upsilon 🤤	<b>4</b>	¥ 🖆			

Channels occupy a flat namespace, i.e., there is no hierarchy in channel names.

By default, images are loaded into the same channel you are currently viewing (unless your viewer has been customized to load images according to special rules).

**Note:** To keep images organized, simply change to the desired channel before opening a new image, or drag the image to the desired channel viewer.

Many preferences in Ginga are set on a per-channel basis. Some per-channel settings include:

• Color distribution algorithm

- Color map
- Intensity map
- Cut levels
- Auto cut levels algorihm
- Transforms (flip, swap)
- Rotation
- WCS display coordinates
- Zoom algorithm
- Scale
- Interpolation type
- Pan position

A new channel will generally inherit the settings for the generic *Image* channel until new preferences are defined and saved.

If you create a new channel and had previously saved preferences for a channel with that name, the new channel will adopt those preferences. Thus you can set up channels configured for certain telescopes or for types of data and easily reuse them in later sessions.

Another idea embodied in the channel concept is that the user should not have to manage memory usage too explicitly. Each channel has a setting that limits how many images it should keep in memory. If the number of images exceeds the limit then Ginga will remove older images and load them back in as needed without user intervention.

## 4.2.3 Plugins

Almost all functionality in Ginga is achieved through the use of a plugin architecture.

Plugins are quasi-independent Python modules that can optionally have a Graphical User Interface. If they do have a GUI, it can be loaded at program startup or be dynamically opened and closed during the duration of the viewer's execution.

Plugins can be *global*, in which case they don't have any particular affiliation with a channel and are generally invoked singularly, or *local* in which case they can be invoked in multiple instances–one per channel.

In this documentation we will also use the word *operation* to describe activating a plugin. For example, a "pick" operation would use the Pick plugin.

Plugins are written as encapsulated Python modules that are loaded dynamically when Ginga starts. There is an API for programming plugins (see *Developing with Ginga*).

The plugins are each described in more detail in *Plugins*.

For those plugins that do have a visible interface, the Ginga startup script can map them to certain workspaces. By manipulating this mapping (and manipulating the workspace layout) we can customize to achieve flexible layouts.

In the image at the top, the left workspace contains three global plugin UIs: the Info, Header and Zoom panes. The middle workspace holds all the viewing panes for each channel. The right workspace has the Dialogs, Thumbs, Contents and Error panes. The operation of these plugins is described in *Plugins*.

### 4.2.4 Modes

Ginga provides a number of default bindings for key and pointer actions. However, there are too many different actions to bind to a limited set of keys and pointer buttons. *Modes* allow us to overcome this limitation.

*Modes* are a mechanism that allow Ginga to accommodate many key and pointer bindings for a large number of operations.

Modes are set on a per-channel basis. Pressing a particular mode key in a channel viewer puts that viewer into that mode.

When in a mode, the behavior is that *some* special key, and the cursor and scroll bindings will override the default ones. An adjacent viewer for a different channel may be in a different mode, or no mode.

Note: If a mode does not override a particular binding, the default one will still be active.


Modes have an associated mode type which can be set to one of:

- held: The mode is active while the activating key is held down
- oneshot: The mode is released by initiating and finishing a cursor drag, or when Esc is pressed, if no cursor drag is performed
- locked: The mode is locked until the mode key is pressed again (or Esc)
- softlock: The mode is locked until another mode key is pressed (or Esc)

By default most modes are activated in "oneshot" type, unless the mode lock is toggled. The mode lock is typically toggled in and out of softlock by the l (lowercase letter l) key and "locked" with L.

Modes are usually indicated by a small black rectangle with the mode name in one corner of the viewer, usually in the lower right corner of the viewer.

Note: When the lock is active it is signified by an additional "[SL]" (softlock) or "[L]" (locked) appearing in the mode indicator.



In the above figure, you can see the mode indicator showing that the viewer is in "contrast" mode, with the softlock on. The same information can be seen in the Toolbar plugin. On the Toolbar plugin you can click to set the mode and toggle the lock on/off.

# 4.3 General Operation

This chapter describes the general manipulations of images using Ginga.

For the most part these manipulations apply both to Ginga ImageView classes that can be embedded in a Python application, as well as to the reference viewer distributed with Ginga.

**Note:** In cases where we are referring to something that is only available in the reference viewer these will be prefixed by the notation [RV].

## 4.3.1 Keyboard and mouse operations

In this documentation we will use the following terms to describe the operations performed with the mouse:

- *Click* or *Left-click* means to click on an item with the left mouse button;
- Drag or Left-drag means to click, hold and drag with the left mouse button;
- Scroll means to scroll with the middle mouse wheel or a trackpad/touchpad;
- Scroll-click means to click with the middle mouse wheel/button;
- Scroll-drag means to click, hold and drag with the middle mouse wheel/button;
- *Right-click* means to click on an item with the right mouse button;
- *Right-drag* means to click, hold and drag with the right mouse button.

Mouse operations are also modified by the keyboard buttons Shift, and Ctrl.

*Shift-click* means to press *and hold* the Shift key while clicking with left mouse button. *Shift-right-click* is the same using the right mouse button, etc.

Some mouse-controlled operations in Ginga are initiated by a key stroke. In these cases the key is pressed and released (not held), and then the mouse is used to control the operation. Such operations are either terminated by releasing the mouse button (if the operation employs a drag), and clicking on the image or by pressing the Esc key (if not a drag operation).

**Note:** We describe the standard key and mouse bindings here. However these bindings can be changed completely by the user. For more information on changing the bindings, see Section *Binding Config File*.

## 4.3.2 Loading a FITS image file

There are several ways to load a file into Ginga:

- Ginga supports drag-and-drop in a typical desktop environment, so you can simply drag and drop files from a graphical file manager such as the Mac Finder or Linux Nautilus onto a Ginga viewing pane to load an image.
- [RV] Another way is to invoke the FBrowser plugin, which opens in the *Dialogs* tab. The plugin pane shows file and folder contents and allows navigation up and down the filesystem hierarchy by double-clicking on folder names. Simply navigate to the location of the FITS file and double-click on the file name to load it, or drag it onto the image pane.

• [RV] Use the *Load Image* entry from the File menu on the main menu bar at the top of the window. This opens a standard file dialog popup window where you can navigate to the file you wish to load.

## 4.3.3 Zooming and panning

The display object used throughout most of the Ginga panels has built-in support for zooming and panning. The *Quick Reference* has the complete listing of default keyboard and mouse bindings.

For example:

- The scroll wheel of the mouse can be used to zoom in and out, along with the "+" and "-" keys.
- The backquote key will fit the image to the window.
- Digit keys (1, 2, etc.) will zoom in to the corresponding zoom level, while holding Shift and pressing a zoom key zooms out to the corresponding level.

When zoomed in, panning is enabled. Panning takes two forms:

 Proportional panning or "drag panning" pans the image in direct proportion to the distance the mouse is moved. You can think of this as dragging the image canvas in the direction you want to move it under the window portal. To utilize a proportional pan, Ctrl-drag the canvas, or press Space followed by "q" to go into pan mode, and then drag the canvas.

2) *Free panning* allows scrolling around the entire image by mapping the entire image boundaries to the window boundaries. For example, moving the mouse to the upper right-hand corner of the window will pan to the upper right hand corner of the image, etc. You can think of this mode as moving the window portal around over the canvas. To initiate a free pan, press Space followed by "w" to enter "freepan" mode and then Scroll-drag to move around the window.

[RV] The Pan plugin (usually embedded under the *Info* tab) shows the outline of the current pan position as a rectangle on a small version of the whole image. Dragging this outline will also pan the image in the main window. You can also click anywhere in the Pan window to set the pan position, or right drag an outline to roughly specify the region to zoom and pan to together.

#### Pan position

Panning in Ginga is based on an (X, Y) coordinate known as the *pan position*. The pan position determines what Ginga will try to keep in the middle of the window as the image is zoomed.

When zoomed out, you can Shift-click on a particular point in the image (or press the "p" key while hovering over a spot), setting the pan position. Zooming afterward will keep the pan position in the center of the window. To reset the pan position to the center of the image, press 'c'.

Ginga has an auto zoom feature to automatically fit newly loaded images to the window, similar to what happens when the backquote key is pressed. See "Zoom Preferences" section in *Preferences* for details.

### 4.3.4 How Ginga maps an image to color

The process of mapping a monochrome science image to color in Ginga involves four steps, in order:

- 1) Applying the *cut levels*, which scales all values in the image to a specified range<sup>1</sup>,
- 2) Applying a *color distribution algorithm*, which distributes values within that range to indexes into a color map table, and
- 3) Applying a *shift map*, which shifts and stretches or shrinks the values according to the user's contrast adjustment<sup>2</sup>, and finally,
- 4) Applying an *intensity map* and *color map* to map the final output to RGB pixel values.

#### Setting cut levels

When visualizing pixel data with an arbitrary value range, the range is first scaled into a limited range based on the low and high *cut levels* defined in the view object. These cut levels can be set manually by the user or automatically based on an algorithm. This eliminates the effect of outlier pixel/flux values.

#### Manually setting cut levels

There are several ways to manually set the cut levels:

- Pressing Space followed by "s" key will put the viewer into "cuts" mode. Here you can invoke a dual (high and low) interactive cut levels. Click and drag the mouse horizontally in the window to interactively set the high level, and vertically to set the low level; and when you reach the desired levels, release the mouse button. Scrolling the mouse wheel in this mode will also change the low and high cut levels simultaneously–toward or away from each other, resulting in lower or higher contrast.
- [RV] The "Cut Low" and "Cut High" boxes in the Info plugin panel can be used. The current values are shown to the left; simply type a new value in the corresponding box and press Enter or click the "Cut Levels" button below. Cut values can also be set from the "Histogram" plugin.

#### Automatically setting cut levels

Ginga can algorithmically estimate and set the cut levels-called *auto (cut) levels*. To activate the auto levels:

- Press the ("a") key when the viewing widget has the focus.
- [RV] Click the "Auto Levels" button in the Info plugin panel.

[RV] The auto cut levels feature is controlled by several factors in the preferences, including the choice of algorithm and some parameters to the algorithm. See "Auto Cuts Preferences" section in *Preferences* for details.

Ginga can also automatically set the cut levels for new images displayed in the view. See "New Image Preferences" section in *Preferences* for details.

<sup>&</sup>lt;sup>1</sup> Some image viewers or graphing programs use the term "limits" for what we call "cut levels".

<sup>&</sup>lt;sup>2</sup> What some programs call a "contrast/bias" adjustment.

#### Setting the color distribution algorithm

Ginga supports a number of color scale distribution algorithms, including:

- "linear",
- "log",
- "power",
- "sqrt",
- "squared",
- "asinh",
- "sinh", and
- "histeq" (histogram equalization).

These can be sampled with the current color and intensity maps by pressing Space followed by "d" key to go into "dist" mode, and then scrolling the mouse, pressing the up/down keys, or the "b" and "n" keys.

Press Esc to exit the "dist" mode.

To reset to the default ("linear") map, press "D" (capital D).

[RV] The color scale distribution algorithms can also be set from the Preferences plugin, under the heading "Color Distribution".

#### Making contrast adjustments

The value range can be shifted and stretched or squeezed to alter the visibility and contrast of the image. This is sometimes called a "bias/contrast" adjustment in other viewers.

In most Ginga configurations the shift map adjustment is bound to the Ctrl-right drag combination (hold Ctrl down and right drag). Dragging left/right shifts the map, and up/down stretches or shrinks the map.

You can also press "t" to enter "contrast" mode, where you can then use a regular Left-drag.

#### Changing the color and intensity maps

The color and intensity maps control the final mapping of colors to the values in the image.

#### **Intensity Maps**

Intensity maps are available to produce a final permutation on the value range of the image before color is applied. The function of these largely overlaps the function of the color distribution algorithm, so *most users will typically use either one or the other, but not both.* 

For example, the intensity map "log" essentially applies a log distribution to the range. If this has already been done with the color distribution "log", the effect is doubly applied.

Possible values for the intensity map are:

- "equa",
- "expo",
- "gamma",

- "jigsaw",
- "lasritt",
- "log",
- "neg",
- "neglog",
- "null", "ramp" and
- "stairs".

"ramp" is the default value.

While in "cmap" mode (described below), the "j" and "k" keys can be used to cycle through the intensity maps.

#### **Color Maps**

To change color maps from the keyboard shortcuts, press Space followed by "y" to go into "cmap" mode. While in "cmap" mode you can change color maps by scrolling the mouse, pressing the up/down keys, or the "b" and "n" keys.

While in "cmap" mode, pressing "I" (uppercase) will invert the current color map. Press Esc to exit cmap mode.

**Note:** Setting a new color map will cancel the color map inversion. Some color maps are available in both regular and inverted forms. If selecting an already inverted (aka "reversed") color map it is not necessary to explicitly invert it.

While many color maps are available built in, users can also define their own color maps or use matplotlib color maps, if the matplotlib package is installed.

[RV] The ColorMapPicker global plugin is useful you to visualize all of the colormaps and apply one to the currently active channel viewer.

### 4.3.5 Transforming the image view

Ginga provides several controls for transforming the image view. The image can be flipped in the X axis ("horizontally"), Y axis ("vertically"), have the X and Y axes swapped, or any combination thereof. These operations can be done by keyboard shortcuts:

- Press "[" to flip in X, "{" to restore.
- Press "]" to flip in Y, "}" to restore.
- Press "" to swap X and Y axes, "I" to restore.

The image can also be rotated in arbitrary amounts.

An interactive rotate operation can be initiated by pressing Space follwed by "r" in the image and then dragging the mouse horizontally left or right to set the angle. Press "R" (Shift+R) to restore the angle to 0 (unrotated).

**Note:** It is less computationally-intensive to rotate the image using the simple transforms (flip, swap) than by the rotation feature. Rotation may slow down some viewing operations.

[RV] The image can also be transformed in the channel *Preferences* (see "Transform Preferences") which has checkboxes for flip X, flip Y, swap XY and a box for rotation by degrees.

# 4.4 Plugins

Ginga is written so that most of the functionality of the program is achieved through the use of plugins. This modular approach allows a large degree of flexibility and customization, as well as making overall design and maintenance of the program simpler.

Plugins are divided into two types: *global* and *local*. A global plugin has a single instance shared by all channels, while a local plugin creates a unique instance for each channel. If you switch channels, a global plugin will respond to the change by updating itself, while a local plugin will remain unchanged if the channel is switched, because its operation is specific to a given channel. (Ginga's concept of channels is discussed in *Channels*.)

This chapter describes the set of plugins that come with Ginga. Those interested in writing their own custom plugins should refer to *Writing a Global Plugin* or *Anatomy of a Local Ginga Plugin*.

## 4.4.1 Global plugins

#### Toolbar

Toolbar provides a set of convenience UI controls for common operations on viewers.


#### Plugin Type: Global

Toolbar is a global plugin. Only one instance can be opened.

#### Usage

Hovering over an icon on the toolbar should provide you with usage tool tip.

#### Pan



The Pan plugin provides a

small panning image that gives an overall "birds-eye" view of the channel image that last had the focus. If the channel image is zoomed in 2X or greater, then the pan region is shown graphically in the Pan image by a rectangle.

#### **Plugin Type: Global**

Pan is a global plugin. Only one instance can be opened.

#### Usage

The channel image can be panned by clicking and/or dragging to place the rectangle. Using the right mouse button to drag a rectangle will force the channel image viewer to try to match the region (taking into account the differences in the aspect ratio between the drawn rectangle and the window dimensions). Scrolling in the Pan image will zoom the channel image.

The color/intensity map and cut levels of the Pan image are updated when they are changed in the corresponding channel image. The Pan image also displays the World Coordinate System (WCS) compass, if valid WCS metadata is present in the FITS HDU being viewed in the channel.

The Pan plugin usually appears as a sub-pane under the "Info" tab, next to the Info plugin.

This plugin is not usually configured to be closeable, but the user can make it so by setting the "closeable" setting to True in the configuration file–then Close and Help buttons will be added to the bottom of the UI.

#### Info

```
Synopsis Command
     Name: SUPA01118784[PRIMARY,1]
    Object: M27
         X: 504.773
         Y: 1494.557
     Value: 488
         a: 19:59:08.977
         δ: +22:32:17.112
   Equinox: 2000.0
Dimensions: 2272x4273
       Min: 137
      Max: 65535
      Zoom: 1/3.57x
    Cut Low: 141
   Cut High: 1086
Auto Levels
                         Cut Levels
   Cut New: override
 Zoom New: on
Center New: off
```

The Info plugin provides a pane of

commonly useful metadata about the associated channel image. Common information includes some metadata header values, coordinates, dimensions of the image, minimum and maximum values, etc. As the cursor is moved around the image, the X, Y, Value, RA, and DEC values are updated to reflect the value under the cursor.

#### **Plugin Type: Global**

Info is a global plugin. Only one instance can be opened.

#### Usage

At the bottom of the Info interface the cut levels controls. Here the low and high cut levels are shown and can be adjusted. Pressing the "Auto Levels" button will recalculate cut levels based on the current auto cut levels algorithm and parameters defined in the channel preferences.

Below the "Auto Levels" button, the status of the settings for "Cut New", "Zoom New", and "Center New" are shown for the currently active channel. These indicate how new images that are added to the channel will be affected by auto cut levels, fitting to the window and panning to the center of the image.

The "Follow New" checkbox controls whether the viewer will automatically display new images added to the channel. The "Raise New" checkbox controls whether an image viewer window is raised when a new image is added. These two controls can be useful, for example, if an external program is adding images to the viewer, and you wish to prevent interruption of your work examining a particular image. As a global plugin, Info responds to a change of focus to a new channel by displaying the metadata from the new channel. It typically appears under the "Synopsis" tab in the user interface.

This plugin is not usually configured to be closeable, but the user can make it so by setting the "closeable" setting to True in the configuration file–then Close and Help buttons will be added to the bottom of the UI.

#### Header

Info	Header	Zoom						
Keyword		Value	Â					
SIMPLE		Тгие						
В	ITPIX	16						
NAXIS		2						
NAXIS1		2272						
N	AXIS2	4273						
E	XTEND	False						
B	ZERO	32768.0						
B	SCALE	1.0						
В	UNIT	ADU	U					
В	LANK	-32768						
D	ATE-OBS	2009-08-22						
U	Т	09:34:25.911						
U	T-STR	09:34:25.911						
U	T-END	09:35:55.010						
Н	ST	23:34:25.911						
H	ST-STR	23:34:25.911						
Н	ST-END	23:35:55.010						
LS	ST	21:15:48.968						
LS	ST-STR	21:15:48.968						
LS	ST-END	21:17:18.311						
M	JD	55065.398914						
TI	MESYS	UTC						
		55065.398914						
M	JD-END							
		17.858						
Z	D-END	18.2						
S	ECZ-STR	1.051						
S	ECZ-END	1.053						
Α	IRMASS	1.0526						
A	ZIMUTH	282.679						
		72.142						
P	ROP-ID	099005						
0	BSERVER	Jeschke, Inagaki, Streeper,						
		SUPA01118760						
	XP-ID	SUPE01118760						
D	ATASET	DS000						
0	BS-MOD	IMAG_N_VGW						
	BS-ALOC	Observation						
	ATA-TYP	OBJECT						
OBJECT		M27						
R		19·59·40 168	J					
	rtable							

The Header plugin provides a listing of the metadata associated

with the image.

#### Plugin Type: Global

Header is a global plugin. Only one instance can be opened.


#### Usage

The Header plugin shows the FITS keyword metadata from the image. Initially only the Primary HDU metadata is shown. However, in conjunction with the MultiDim plugin, the metadata for other HDUs will be shown. See MultiDim for details.

If the "Sortable" checkbox has been checked in the lower left of the UI, then clicking on a column header will sort the table by values in that column, which may be useful for quickly locating a particular keyword.

If the "Include primary header" checkbox toggles the inclusion of the primary HDU keywords or not. This option may be disabled if the image was created with an option not to save the primary header.

### Zoom



The Zoom plugin shows an enlarged image of a cutout region centered under the cursor position in the associated channel image. As the cursor is moved around the image, the zoom image updates to allow close inspection of the pixels or precise control in conjunction with other plugin operations.

#### Plugin Type: Global

Zoom is a global plugin. Only one instance can be opened.

#### Usage

The magnification of the zoom window can be changed by adjusting the "Zoom Amount" slider.


Two modes of operation are possible – absolute and relative zoom:

- In absolute mode, the zoom amount controls exactly the zoom level shown in the cutout; For example, the channel image may be zoomed into 10X, but the zoom image will only show a 3X image if the zoom amount is set to 3X.
- In relative mode, the zoom amount setting is interpreted as relative to the zoom setting of the channel image. If the zoom amount is set to 3X and the channel image is zoomed to 10X then the zoom image shown will be 13X (10X + 3X). Note that the zoom amount setting can be < 1, so a setting of 1/3X with a 3X zoom in the channel image will produce a 1X zoom image.

The "Refresh Interval" setting controls how quickly the Zoom plugin responds to the movement of the cursor in updating the zoom image. The value is specified in milliseconds.

**Tip:** Usually setting a small refresh interval *improves* the overall responsiveness of the zoom image, and the default value of 20 is a reasonable one. You can experiment with the value if the zoom image seems too jerky or out of sync with the mouse movement in the channel image window.

The "Defaults" button restores the default settings of the controls.



### Thumbs

✓ Auto scroll

The Thumbs plugin provides a

thumbnail index of all images viewed since the program was started.

### **Plugin Type: Global**

Thumbs is a global plugin. Only one instance can be opened.

#### Usage

By default, Thumbs appear in cronological viewing history, with the newest images at the bottom and the oldest at the top. The sorting can be made alphanumeric by a setting in the "plugin\_Thumbs.cfg" configuration file.

Clicking on a thumbnail navigates you directly to that image in the associated channel. Hovering the cursor over a thumbnail will show a tool tip that contains a couple of useful pieces of metadata from the image.

The "Auto Scroll" checkbox, if checked, will cause the Thumbs pan to scroll to the active image.

This plugin is not usually configured to be closeable, but the user can make it so by setting the "closeable" setting to True in the configuration file–then Close and Help buttons will be added to the bottom of the UI.

#### Contents

Dialogs	Thumbs	Contents	Errors					
Name				Object		Date	Time UT	Modified
▼ VGW								
VC	WA0046	6652[PRIM	ARY,1]	RegionSelect	tion	2006-05-10	10:28:39.281	None
VC	WA0046	0883[PRIM	ARY,1]	Focusing		2006-05-02	09:37:34.022	None
VC	WA0046	0869[PRIM	ARY,1]	Focusing		2006-05-02	09:36:22.490	None
SPCA								
SU	PA01118	789[PRIMA	ARY,1]	M27		2009-08-22	09:39:06.270	None
		788[PRIMA		M27		2009-08-22	09:39:06.270	None
		787[PRIMA		M27		2009-08-22	09:39:06.270	None
		781[PRIMA		M27		2009-08-22	09:39:06.270	None
SU	PA01118	780[PRIMA	ARY,1]	M27		2009-08-22	09:39:06.270	None
		779[PRIMA		M27		2009-08-22	09:36:45.102	None
SU	PA01118	778[PRIM	ARY,1]	M27		2009-08-22	09:36:45.102	None
<ul> <li>MOIF</li> </ul>								
		8063[PRIM			CENTER		09:11:18.294	
		5490[PRIM/		DOMEFLAT		2011-09-27	16:00:24.154	None
		6489[PRIM		DOMEFLAT			16:00:24.154	
		975[PRIM		4C23.56MOS	5		08:43:04.682	
	CSA00185	927[PRIM	ARY,1]	HIP101748		2011-09-27	07:10:26.265	None
→ HSC								
		025[PRIMA		SSP-Wide			06:46:47.656	
		024[PRIMA		SSP-Wide			06:46:47.656	
HS	CA08092	023[PRIMA	ARY,1]	SSP-Wide		2016-08-01	06:46:47.656	None
		$\sim$				$\frown$	~	~
Displ	ау	Move	Сору	Remo	ve			

The Contents plugin provides a table of contents-like interface for all the images viewed since the program was started. Unlike Thumbs, Contents is sorted by channel. The contents also shows some configurable metadata from the image.

#### **Plugin Type: Global**

Contents is a global plugin. Only one instance can be opened.

#### Usage

Click on a column heading to sort the table by that column; Click again to sort the other way.

**Note:** The columns and their values are drawn from the FITS header, if applicable. This can be customized by setting the "columns" parameter in the "plugin\_Contents.cfg" settings file.


The active image in the currently focused channel will normally be highlighted. Double-click on an image will force that image to be shown in the associated channel. Single-click on any image to activate the buttons at the bottom of the UI:

- "Display": Make the image the active image.
- "Move": Move the image to another channel.
- "Copy": Copy the image to another channel.
- "Remove": Remove the image from the channel.

If "Move" or "Copy" is done on an image that has been modified in Ginga (which would have an entry under ChangeHistory, if used), the modification history will be retained as well. Removing an image from a channel destroys any unsaved changes.

This plugin is not usually configured to be closeable, but the user can make it so by setting the "closeable" setting to True in the configuration file–then Close and Help buttons will be added to the bottom of the UI.

## Colorbar



The Colorbar plugin shows a colorbar indicating the colormap applied to the image and showing the example values along the range.

## **Plugin Type: Global**

Colorbar is a global plugin. Only one instance can be opened.

#### Usage

Clicking and dragging in the Colorbar window will shift the colormap left or right. Scrolling will stretch or shrink the colormap at the cursor position. Right-clicking will restore the colormap from any shift or stretch.

If the focus shifts to another channel, the colorbar will be updated to reflect that channel's colormap and value information.

## Cursor

5						
252.2 214.5	376.7 430.9	501.1 503.4	025.0 007.0	740.4 700.1	830 0 889 7	939.5
α: 20:00:33.619 δ:	+22:36:15.967	X: 1315.595	Y: 2512.550	Value: 452		
Image : Operation						

The Cursor plugin displays a summary line of text that changes as the user moves the cursor around an image. In the standard reference viewer configuration, it appears as a line containing green text just below the Colorbar plugin.

## Plugin Type: Global

Cursor is a global plugin. Only one instance can be opened.

#### Usage

Cursor simply tracks the cursor as it moves around an image and displays information about the pixel coordinates, WCS coordinates (if available) and the value of the pixel under the cursor.

There is no associated configuration GUI.

**Note:** Pixel coordinates are affected by the general setting "pixel\_coords\_offset" which can be set in the "general.cfg" configuration file for ginga. The default is value for this setting is 1.0, which means pixel coordinates are reported from an origin of 1, as per the FITS standard.

# **Operations**

This plugin defines the GUI for managing local plugins, a.k.a., "operations".

## **Plugin Type: Global**

Operations is a global plugin. Only one instance can be opened.

Usage

The Operations plugin acts as a visual interface to the reference viewer plugin manager. With this plugin, you can change the active channel, start, stop, or unfocus a local plugin on a channel, and see which local plugins are running.

**Note:** By replacing or subclassing this plugin, you can customize the way the reference viewer starts and manages operations.

## WBrowser

Web browser plugin for Ginga.

#### Plugin Type: Global

WBrowser is a global plugin. Only one instance can be opened.

## Usage


This global plugin is used to browse help pages for Ginga.

When a "Help" button is pressed from a plugin (e.g., Pick), Ginga will attempt to download an existing documentation build from *ReadTheDocs* for the matching version. If successful, plugin documentation from that download is displayed. If not successful or deliberately disabled in "plugin\_WBrowser.cfg", Ginga will render the plugin's docstring locally.

# FBrowser (Open File)

This brings up *FBrowser* local plugin from the global menu for convenience.

# ColorMapPicker



to graphically browse and select a colormap for a channel image viewer.

## Plugin Type: Global

ColorMapPicker is a global plugin. Only one instance can be opened.

#### Usage

Operation of the plugin is very simple: the colormaps are displayed in the form of colorbars and labels in the main view pane of the plugin. Click on any one of the bars to set the colormap of the currently active channel in the viewer.

Change the channel to set the colormap on a different channel.

You can scroll vertically or use the scroll bars to move through the colorbar samples.

**Note:** When the plugin starts for the first time, it will generate a bitmap RGB image of colorbars and labels corresponding to all the available colormaps. This can take a few seconds depending on the number of colormaps installed.

Colormaps are shown with the "ramp" intensity map applied.

## **Errors**

The Errors plugin reports error messages on the viewer.

## Plugin Type: Global

Errors is a global plugin. Only one instance can be opened.

#### Usage

When an error occurs in Ginga, its message may be reported here.

This plugin is not usually configured to be closeable, but the user can make it so by setting the "closeable" setting to True in the configuration file–then Close and Help buttons will be added to the bottom of the UI.

## RC

The RC plugin implements a remote control interface for the Ginga viewer.

## **Plugin Type: Global**

RC is a global plugin. Only one instance can be opened.

#### Usage

The RC (Remote Control) plugin provides a way to control Ginga remotely through the use of an XML-RPC interface. Start the plugin from the "Plugins" menu (invoke "Start RC") or launch ginga with the --modules=RC command line option to start it automatically.

By default, the plugin starts up with server running on port 9000 bound to the localhost interface – this allows connections only from the local host. If you want to change this, set the host and port in the "Set Addr" control and press Enter – you should see the address update in the "Addr:" display field.

Please note that the host part (before the colon) does not indicate *which* host you want to allow access from, but to which interface to bind. If you want to allow any host to connect, leave it blank (but include the colon and port number) to allow the server to bind on all interfaces. Press "Restart" to then restart the server at the new address.

Once the plugin is started, you can use the ggrc script (included when ginga is installed) to control Ginga. Take a look at the script if you want to see how to write your own programmatic interface.

Show example usage:

\$ ggrc help

Show help for a specific Ginga method:

\$ ggrc help ginga <method>

Show help for a specific channel method:

\$ ggrc help channel <chname> <method>

Ginga (viewer shell) methods can be called like this:

\$ ggrc ginga <method> <arg1> <arg2> ...

Per-channel methods can be called like this:

\$ ggrc channel <chname> <method> <arg1> <arg2> ...

Calls can be made from a remote host by adding the options:

--host=<hostname> --port=9000

(In the plugin GUI, be sure to remove the "localhost" prefix from the "addr", but leave the colon and port.)

#### Examples

Create a new channel:

```
$ ggrc ginga add_channel FOO
```

Load a file:

\$ ggrc ginga load\_file /home/eric/testdata/SPCAM/SUPA01118797.fits

Load a file into a specific channel:

\$ ggrc ginga load\_file /home/eric/testdata/SPCAM/SUPA01118797.fits FO0

Cut levels:

\$ ggrc channel FOO cut\_levels 163 1300

Auto cut levels:

\$ ggrc channel FOO auto\_levels

Zoom to a specific level:

\$ ggrc -- channel FOO zoom\_to -7

(Note the use of -- to allow us to pass a parameter beginning with -.)

Zoom to fit:

\$ ggrc channel FOO zoom\_fit

Transform (arguments are a boolean triplet: flipx flipy swapxy):

\$ ggrc channel FOO transform 1 0 1

Rotate:

\$ ggrc channel FOO rotate 37.5

Change colormap:

\$ ggrc channel FOO set\_color\_map rainbow3

Change color distribution algorithm:

\$ ggrc channel FOO set\_color\_algorithm log

Change intensity map:

\$ ggrc channel FOO set\_intensity\_map neg

In some cases, you may need to resort to shell escapes to be able to pass certain characters to Ginga. For example, a leading dash character is usually interpreted as a program option. In order to pass a signed integer, you may need to do something like:

\$ ggrc -- channel FOO zoom -7

#### Interfacing from within Python

It is also possible to control Ginga in RC mode from within Python. The following describes some of the functionality.

Connecting

First, launch Ginga and start the RC plugin. This can be done from the command line:

```
ginga --modules=RC
```

From within Python, connect with a RemoteClient object as follows:

```
from ginga.util import grc
host='localhost'
port=9000
viewer = grc.RemoteClient(host, port)
```

This viewer object is now linked to the Ginga using RC.

Load an Image

You can load an image from memory in a channel of your choosing. First, connect to a channel:

ch = viewer.channel('Image')

Then, load a Numpy image (i.e., any 2D ndarray):

```
import numpy as np
img = np.random.rand(500, 500) * 10000.0
ch.load_np('Image_Name', img, 'fits', {})
```

The image will display in Ginga and can be manipulated as usual.

Overlay a Canvas Object

It is possible to add objects to the canvas in a given channel. First, connect:

canvas = viewer.canvas('Image')

This connects to the channel named "Image". You can clear the objects drawn in the canvas:

```
canvas.clear()
```

You can also add any basic canvas object. The key issue to keep in mind is that the objects input must pass through the XMLRC protocol. This means simple data types (float, int, list, or str); No arrays. Here is an example to plot a line through a series of points defined by two Numpy arrays:

```
x = np.arange(100)
y = np.sqrt(x)
points = list(zip(x.tolist(), y.tolist()))
canvas.add('path', points, color='red')
```

This will draw a red line on the image.

# WCSMatch

WCS Match	
Reference Channel: None	•
Close Help	

WCSMatch is a global plugin for the

Ginga image viewer that allows you to roughly align images with different scales and orientations using the images' World Coordinate System (WCS) for viewing purposes.

# Plugin Type: Global

WCSMatch is a global plugin. Only one instance can be opened.

## Usage

To use, simply start the plugin, and from the plugin GUI select a channel from the drop-down menu labeled "Reference Channel". The image contained in that channel will be used as a reference for synchronizing the images in the other channels.

The channels will be synchronized in viewing (pan, scale (zoom), transforms (flips) and rotation. The checkboxes "Match Pan", "Match Scale", "Match Transforms" and "Match Rotation" can be checked or not to control which attributes are synchronized between channels.

To completely "unlock" the synchronization, simply select "None" from the "Reference Channel" drop-down menu.

Currently, there is no way to limit the channels that are affected by the plugin.

# ChangeHistory

Timesta	amp (UTC)		~	Description	
✓ Imag					
⊽ jb	5s01fnq_b	lv_tmp[SC	[,1]		
10	2016-01-	21Z 20:14	:11Z	SNR* and SBR	keyword.
	2016-01-	21Z 20:15	:01Z	44.113018035	59 subtrac
⊽ jb	6e07dmq	blv_tmp[S	SCI,1]		
	2016-01-	21Z 20:16	:13Z	SNR* and SBR	keyword.
🗢 Imag	le3				
⊽ jc	7f01jbq_ra	w[SCI,1]			
	2016-01-	21Z 20:17	:20Z	2202.0 subtra	cted from.
		Selec	ted His	story	
			ted His		
		Chanr Ima	nel: Ima ge: jb5	ige s01fnq_blv_tmp	
		Chanr Ima	nel: Ima ge: jb5	ige	
Descrir	otion:-	Chanr Ima	nel: Ima ge: jb5	ige s01fnq_blv_tmp	
		Chanr Ima Timestar	nel: Ima ge: jb5 np: 201	nge s01fnq_blv_tmp 16-01-21Z 20:14	
	and SBR ke	Chanr Ima Timestar eywords u	nel: Ima ge: jb5 np: 201 pdated	nge s01fnq_blv_tmp L6-01-21Z 20:14	
SNR* a jb5s01 y=946	and SBR ke Ifnq_blv_tr 5.5906122	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[	nel: Ima ge: jb5 np: 201 pdated x=691 694.65	age s01fnq_blv_tmp 16-01-21Z 20:14 in 1.706192688, 43408360128,	4:11Z
SNR* a jb5s01 y=946 949.84	and SBR ke lfnq_blv_tr 5.5906122 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69	pdated x=691 694.6543	age s01fnq_blv_tmp 16-01-21Z 20:14 in 1.706192688, 43408360128, 4408360128,	4:11Z
SNR* a jb5s01 y=946 949.84 949.84	and SBR ke Ifnq_blv_tr 5.5906122 440514469 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69	pdated x=691 694.65 4.6543	age s01fnq_blv_tmp 16-01-21Z 20:14 in 1.706192688, 43408360128, 4408360128, 4408360128,	4:11Z
SNR* 2 jb5s01 y=946 949.84 949.84 949.84	and SBR ke lfnq_blv_tr 5.5906122 440514469 440514469 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69 9453], [69	pdated x=691 694.65 4.6543 5.1543	age s01fnq_blv_tmp 16-01-21Z 20:14 1 1.706192688, 43408360128, 4408360128, 4408360128, 4408360128,	4:11Z
SNR* a jb5s01 y=946 949.84 949.84 947.84 947.84	and SBR ke lfnq_blv_tr 5.5906122 440514469 440514469 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69 9453], [69 9453], [69	nel: Ima ge: jb5 np: 201 pdated x=691 694.65 4.6543 5.1543 5.1543 5.1543	age s01fnq_blv_tmp 16-01-21Z 20:14 1 1.706192688, 43408360128, 4408360128, 4408360128, 4408360128, 4408360128,	4:11Z
SNR* 2 jb5s01 y=946 949.84 949.84 947.84 947.84 947.84 946.84	and SBR ka lfnq_blv_tr 5.5906122 440514469 440514469 440514469 440514469 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69 9453], [69 9453], [69 9453], [69	nel: Ima ge: jb5 np: 201 pdated x=691 694.65 4.6543 5.1543 5.1543 5.6543 6.1543	age s01fnq_blv_tmp 16-01-21Z 20:14 1 in 1.706192688, 43408360128, 408360128, 408360128, 408360128, 408360128, 408360128, 408360128,	4:11Z
SNR* 2 jb5s01 y=946 949.84 949.84 947.84 947.84 947.84 946.84 945.34	and SBR kc lfnq_blv_tr 5.5906122 440514469 440514469 440514469 440514469 440514469 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69 9453], [69 9453], [69 9453], [69 9453], [69	nel: Ima ge: jb5 np: 201 pdated x=691 694.65 4.6543 5.1543 5.1543 5.6543 6.1543 6.1543	age s01fnq_blv_tmp 16-01-21Z 20:14 10 1.706192688, 43408360128, 408360128, 408360128, 408360128, 408360128, 408360128, 408360128, 408360128, 408360128,	4:11Z
SNR* 4 jb5s01 y=946 949.84 949.84 947.84 947.84 947.84 947.84 945.34 944.84	and SBR kc 1fnq_blv_tr 5.5906122 440514469 440514469 440514469 440514469 440514469 440514469 440514469	Chanr Ima Timestar eywords u np[SCI,1]; 93, pts=[[ 9453], [69 9453], [69 9453], [69 9453], [69 9453], [69 9453], [69	nel: Ima ge: jb5 np: 201 pdated x=691 694.65 4.6543 5.1543 5.1543 5.1543 6.1543 6.1543 6.1543	age s01fnq_blv_tmp 16-01-21Z 20:14 1 in 1.706192688, 43408360128, 408360128, 408360128, 408360128, 408360128, 408360128, 408360128,	4:11Z

Keep track of buffer change history.

## **Plugin Type: Global**

ChangeHistory is a global plugin. Only one instance can be opened.

This plugin is used to log any changes to data buffer. For example, a change log would appear here if a new image is added to a mosaic via the Mosaic plugin. Like Contents, the log is sorted by channel, and then by image name.

## Usage

History should stay no matter what channel or image is active. New history can be added, but old history cannot be deleted, unless the image/channel itself is deleted.


The redo() method picks up an 'add-image-info' event and displays related metadata here. The metadata is

obtained as follows:

```
channel = self.fv.get_channel_info(chname)
iminfo = channel.get_image_info(imname)
timestamp = iminfo.time_modified
description = iminfo.reason_modified  # Optional
```

Both 'time\_modified' and 'reason\_modified' have to be explicitly set by the calling plugin in the same method that issues the 'add-image-info' callback, like this:

## **SAMP Control**



implements a SAMP interface for the Ginga reference viewer.

The SAMP plugin

Note: To run this plugin, you need to install astropy that has the samp module.

## Plugin Type: Global

SAMP is a global plugin. Only one instance can be opened.

#### Usage

Ginga includes a plugin for enabling SAMP (Simple Applications Messaging Protocol) support. With SAMP support, Ginga can be controlled and interoperate with other astronomical desktop applications.

The SAMP module is not started by default. To start it when Ginga starts, specify the command line option:

--modules=SAMP

Otherwise, start it using "Start SAMP" from the "Plugins" menu.

Currently, SAMP support is limited to image.load.fits messages, meaning that Ginga will load a FITS file if it receives one of these messages.

Ginga's SAMP plugin uses the astropy.samp module, so you will need to have astropy installed to use the plugin. By default, Ginga's SAMP plugin will attempt to start a SAMP hub if one is not found running.

Log

Dialogs Thumbs Contents Errors	; Log	
2017-04-10 17:39:32,341   D 2017-04-10 17:39:32,341   D 2017-04-10 17:39:32,341   D 2017-04-10 17:39:32,341   D 2017-04-10 17:39:32,341   D 2017-04-10 17:39:32,341   D 2017-04-10 17:39:32,342   D 2017-04-10 17:39:32,342   D 2017-04-10 17:39:32,342   D 2017-04-10 17:39:32,342   D 2017-04-10 17:39:32,342   D 2017-04-10 17:39:32,348   D 2017-04-10 17:39:32,348   D 2017-04-10 17:39:32,348   D 2017-04-10 17:39:32,348   D 2017-04-10 17:39:32,348   D 2017-04-10 17:39:32,379   D 2017-04-10 17:39:32,381   D 2017-04-10 17:39:32,381   D 2017-04-10 17:39:32,388   D 2017-04-10 17:39:32,388   D 2017-04-10 17:39:32,388   D 2017-04-10 17:39:32,388   D 2017-04-10 17:39:32,388   D 2017-04-10 17:39:32,388   D	<ul> <li>ImageView.py:1142</li> <li>ImageView.py:1439</li> <li>ImageView.py:1508</li> <li>ImageView.py:1527</li> <li>ImageView.py:1536</li> <li>ImageView.py:1540</li> <li>ImageView.py:1390</li> <li>ImageViewQt.py:172</li> <li>ImageViewQt.py:172</li> <li>ImageViewQt.py:142</li> <li>ImageView.py:142</li> <li>ImageView.py:142</li> <li>ImageView.py:142</li> <li>ImageView.py:1439</li> <li>AutoCuts.py:73 (cut imageView.py:1508</li> <li>ImageView.py:1536</li> <li>ImageView.py:1536</li> <li>ImageView.py:1536</li> <li>ImageView.py:1536</li> <li>ImageView.py:1540</li> <li>ImageView.py:1540</li> <li>ImageView.py:1540</li> <li>ImageView.py:1390</li> </ul>	(redraw_now)   widget 'channel:Image' redraw (\ (_calc_bg_dimensions)   approx area covered is ( (apply_transforms)   reshape time 0.000 sec (apply_transforms)   rotate time 0.000 sec, total (apply_transforms)   ctr=169,13 off=180,180 ds (apply_transforms)   win=339,27 coverage=349 (get_rgb_object)   times: total=0.0005 2 (render_image)   redraw pixmap= <pyqt5.qtgu 5 (render_offscreen)   data shape is 360x360x4 (check_cursor_location)   cursor location change 3 (update_image)   updating window from pixmaj (redraw_now)   widget 'colorbar' redraw (whence tocoords)   ra, dec = 300.023517, 22.760580 (_calc_bg_dimensions)   approx area covered is ( _levels)   loval=148.00 hival=1299.31 '_image)   shape of index is (434, 231) (apply_transforms)   reshape time 0.000 sec (apply_transforms)   rotate time 0.000 sec, total (apply_transforms)   ctr=168,217 off=285,285 d (apply_transforms)   win=337,435 coverage=45 (get_rgb_object)   times: total=0.0089</pyqt5.qtgu 
2017-04-10 17:39:32,387   D 2017-04-10 17:39:32,388   D	)   ImageView.py:1508 )   ImageView.py:1527	(apply_transforms)   reshape time 0.000 sec (apply_transforms)   rotate time 0.000 sec, total
2017-04-10 17:39:32,388 D	)   ImageView.py:1540 )   ImageView.py:1390 )   ImageViewQt.py:172	(apply_transforms)   win=337,435 coverage=45
2017-04-10 17:39:40,981	ImageViewQt.py:253   ImageView.py:1142   Log.py:113 (set_logle	8 (_render_offscreen)   data shape is 570x570x4 3 (update_image)   updating window from pixma (redraw_now)   widget 'panimage' redraw (when evel_cb)   GUI log level changed to 'Info'
2017-04-10 17:39:42,261     2017-04-10 17:39:43,660		evel_cb)   GUI log level changed to 'Debug' evel_cb)   GUI log level changed to 'Info'
Info	:	1000
🛛 Auto scroll		Clear
Close Help		

See the logging output of the reference viewer.

## **Plugin Type: Global**

Log is a global plugin. Only one instance can be opened.

#### Usage

The Log plugin builds a UI that includes a large scrolling text widget showing the active output of the logger. The latest output shows up at the bottom. This can be useful for troubleshooting problems.

There are four controls:

- The combo box on the lower left allows you to choose the level of logging desired. The four levels, in order of verbosity are: "debug", "info", "warn", and "error".
- The box with the number on the lower right allows you to set how many lines of input to keep in the display buffer (e.g., keep only the last 1000 lines).
- The checkbox "Auto scroll", if checked, will cause the large text widget to scroll to the end as new log messages are added. Uncheck this if you want to peruse the older messages and study them.
- The "Clear" button is used to clear the text widget, so that only new logging shows up.

## Command

This plugin provides a command line interface to the reference viewer.

**Note:** The command line is for use *within* the plugin UI. If you are looking for a *remote* command line interface, please see the RC plugin.

#### **Plugin Type: Global**

Command is a global plugin. Only one instance can be opened.

#### Usage

Get a list of commands and parameters:

g> help

Execute a shell command:

```
g> !cmd arg arg ...
```

#### Notes

An especially powerful tool is to use the reload\_local and reload\_global commands to reload a plugin when you are developing that plugin. This avoids having to restart the reference viewer and laboriously reload data, etc. Simply close the plugin, execute the appropriate "reload" command (see the help!) and then start the plugin again.

Note: If you have modifed modules *other* than the plugin itself, these will not be reloaded by these commands.

Dialogs	Thumbs	Conte	ents Errors	History	Save I	ile		
			▶ Instructio	ns				
	Chann	el: Im	age		Modifie	ed only		
Path: 🗔			age	U				
<u>/</u>	my/output/	path				Browse		
Suffix: g	jinga							
Image		~	Mod. Ext.				]	
drawi	ng0		None					
jb5s0 mosa		np.fits	DQ,1;SCI,1 None					
	:h1_v0.30_s	sci.fits	None					
	ips_v0.30_s	sci.fits	PRIMARY,1					
							1	
Save	e Cl	ose					a .	
			/				Save image	es to output fi

# SaveImage (Save File)

## **Plugin Type: Global**

SaveImage is a global plugin. Only one instance can be opened.


# Usage

This global plugin is used to save any changes made in Ginga back to output images. For example, a mosaic image that was created by the Mosaic plugin. Currently, only FITS images (single or multiple extensions) are supported.

Given the output directory (e.g., /mypath/outputs/), a suffix (e.g., ginga), an image channel (Image), and a selected image (e.g., imagel.fits), the output file will be /mypath/outputs/imagel\_ginga\_Image. fits. Inclusion of the channel name is optional and can be omitted using plugin configuration file, plugin\_SaveImage.cfg. The modified extension(s) will have new header or data extracted from Ginga, while those not modified will remain untouched. Relevant change log entries from the ChangeHistory global plugin will be inserted into the history of its PRIMARY header.

**Note:** This plugin uses the module <code>astropy.io.fits</code> to write the output images, regardless of what is chosen for <code>FITSpkg</code> in the <code>general.cfg</code> configuration file.

## **Downloads**



Downloads GUI for the Ginga reference viewer.

## **Plugin Type: Global**

Download is a global plugin. Only one instance can be opened.

#### Usage

Open this plugin to monitor the progress of URI downloads. Start it using the "Plugins" or "Operations" menu, and selecting the "Downloads" plugin from under the "Util" category.

If you want to initiate a download, simply drag a URI into a channel image viewer or the Thumbs pane.

You can remove the information about a download at any time by clicking the "Clear" button for its entry. You can clear entries for all downloads by clicking the "Clear All" button at the bottom.

Currently, it is not possible to cancel a download in progress.

#### Settings


The auto\_clear\_download option, if set to True, will cause a download entry to be automatically deleted from the pane when the download completes. It does not remove any downloaded file(s).

The download folder can be user-defined by assigning a value to the "download\_folder" setting in ~/.ginga/general.cfg. If unassigned, it defaults to a folder in the platform-specific default temp directory (as told by the Python 'tempfile' module).

# 4.4.2 Local plugins

An *operation* is the activation of a local plugin to perform some function. The plugin manager toolbar at the bottom of the center pane is the graphical way to start an operation.

## Pick



Perform quick astronomical stellar analysis.

## **Plugin Type: Local**

Pick is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

The Pick plugin is used to perform quick astronomical data quality analysis on stellar objects. It locates stellar candidates within a drawn box and picks the most likely candidate based on a set of search settings. The Full Width Half Max (FWHM) is reported on the candidate object, as well as its size based on the plate scale of the detector. Rough measurement of background, sky level and brightness is also done.

## Defining the pick area

The default pick area is defined as a box of approximately 30x30 pixels that encloses the search area.

The move/draw/edit selector at the bottom of the plugin is used to determine what operation is being done to the pick area:

Readout settings controls Report	
Move O Draw O Edit	
Close	

Fig. 1: "Move", "Draw", and "Edit" buttons.

- If "move" is selected, then you can move the existing pick area by dragging it or clicking where you want the center of it placed. If there is no existing area, a default one will be created.
- If "draw" is selected, then you can draw a shape with the cursor to enclose and define a new pick area. The default shape is a box, but other shapes can be selected in the "Settings" tab.
- If "edit" is selected, then you can edit the pick area by dragging its control points, or moving it by dragging in the bounding box.

After the area is moved, drawn or edited, Pick will perform one of three actions:

- 1. In "Quick Mode" ON, with "From Peak" OFF, it will simply attempt to perform a calculation based on the coordinate under the crosshair in the center of the pick area.
- 2. In "Quick Mode" ON, with "From Peak" ON, it will perform a quick detection of peaks in the pick area and perform a calculation on the first one found, using the peak's coordinates.
- 3. In "Quick Mode" OFF, it will search the area for all peaks and evaluate the peaks based on the criteria in the "Settings" tab of the UI (see "The Settings Tab" below) and try to locate the best candidate matching the settings.

## If a candidate is found

The candidate will be marked with a point (usually an "X") in the channel viewer canvas, centered on the object as determined by the horizontal and vertical FWHM measurements.

The top set of tabs in the UI will be populated as follows:

The "Image" tab will show the contents of the cutout area. The widget in this tab is a Ginga widget and so can be zoomed and panned with the usual keyboard and mouse bindings (e.g., scroll wheel). It will also be marked with a point centered on the object and additionally the pan position will be set to the found center.

The "Contour" tab will show a contour plot. This is a contour plot of the area immediately surrounding the candidate, and not usually encompassing the entire region of the pick area. You can use the scroll wheel to zoom the plot and a click of the scroll wheel (mouse button 2) to set the pan position in the plot.

The "FWHM" tab will show a FWHM plot. The blue lines show measurements in the X direction and the green lines show measurements in the Y direction. The solid lines indicate actual pixel values and the dotted lines indicate the fitted 1D function. The shaded green and blue regions indicate the FWHM measurements.

The "Radial" tab contains a radial profile plot. Plotted points in blue are data values, and a line is fitted to the data.




Fig. 2: "Image" tab of Pick area.




Fig. 3: "Contour" tab of Pick area.




Fig. 4: "FWHM" tab of Pick area.




Fig. 5: "Radial" tab of Pick area.




Fig. 6: "Cut" tab of Pick area.

The "Cuts" tab contains a profile plot for the vertical and horizontal cuts represented by the crosshairs present in "Quick Mode" ON. This plot is updated in real time as the pick area is moved. In "Quick Mode" OFF, this plot is not updated.

		Pick		
Zo	om: 10.49x			
Objec	t_X 1428.649	9	Object_	Y 2162.272
	RA: 19:59:04	.206	DE	C: +22:48:40.10
Equir	nox: 2000.0		Backgroun	d: 451.000
Sky Le	vel: 513.550		Brightnes	s: 1155.796
FWHM	1 X: 2.759		FWHM	Y: 2.648
FWI	HM: 2.704		Star Siz	e: 0.546
Sample A	rea: 31x31	Def	ault Region	Pan to pick
Quick Mo	ode 🗸 From	Peak 🖌 Ce	nter on pic	k
Done				
Stop		100	0%	
Readout	Settings	Controls	Report	

Fig. 7: "Readout" tab of Pick area.

The "Readout" tab will be populated with a summary of the measurements. There are two buttons and three check boxes in this tab:

- The "Default Region" button restores the pick region to the default shape and size.
- The "Pan to pick" button will pan the channel viewer to the located center.
- The "Quick Mode" check box toggles "Quick Mode" on and off. This affects the behavior of the pick region as described above.
- The "From Peak" check box changes the behavior of "Quick Mode" slightly as described above.
- If "Center on pick" is checked, the shape will be recentered on the located center, if found (i.e. the shape "tracks" the pick)

			Pick
Bg cut	Delta bg:	-200.0	0-200
Sky cut	Delta sky:		
Bright cut	Delta bright:	500.0	D 500
Readout S	ettings Contr	ols Re	Report

Fig. 8: "Controls" tab of Pick area.

The "Controls" tab has a couple of buttons that will work off of the measurements.

- The "Bg cut" button will set the low cut level of the channel viewer to the measured background level. A delta to this value can be applied by setting a value in the "Delta bg" box (press "Enter" to change the setting).
- The "Sky cut" button will set the low cut level of the channel viewer to the measured sky level. A delta to this value can be applied by setting a value in the "Delta sky" box (press "Enter" to change the setting).
- The "Bright cut" button will set the high cut level of the channel viewer to the measured sky+brightness levels. A delta to this value can be applied by setting a value in the "Delta bright" box (press "Enter" to change the setting).

The "Report" tab is used to record information about the measurements in tabular form.

By pressing the "Add Pick" button, the information about the most recent candidate is added to the table. If the "Record Picks automatically" checkbox is checked, then any candidates are added to the table automatically.

**Note:** If the "Show candidates" checkbox in the "Settings" tab is checked, then *all* objects found in the region (according to the settings) will be added to the table instead of just the selected candidate.

You can clear the table at any time by pressing the "Clear Log" button. The log can be saved to a table by putting a valid path and filename in the "File:" box and pressing "Save table". File type is automatically determined by the given extension (e.g., ".fits" is FITS and ".txt" is plain text).

## If no candidate is found

If no candidate can be found (based on the settings), then the pick area is marked with a red point centered on the pick area.

The image cutout will be taken from this central area and so the "Image" tab will still have content. It will also be marked with a central red "X".

The contour plot will still be produced from the cutout, and the cuts plot will be updated in "Quick Mode".

All the other plots will be cleared.

		Pick		
RA	DEC	Equinox	Х	Υ
20:00:37	+22:48:04.32	2000.0	1318.43678	2050.1588
20:00:36	+22:48:20.03	2000.0	1398.92996	2127.7651
20:00:35	+22:47:53.63	2000.0	1509.76160	1996.9219 <sup>-</sup>
20:00:37	+22:48:19.74	2000.0	1343.41759	2126.4362
( ( m	)			) D
Add Pick 🛛 R	ecord Picks aut	comatically Cle	ear Log	
Save as FITS ta	able File: pick	log.fits		
Readout Sett	ings Controls	Report		

Fig. 9: "Report" tab of Pick area.




Fig. 10: Marker when no candidate found.




Fig. 11: Contour when no candidate found.

## The Settings Tab

		Pick
Show Candidates		
Draw type: r	rectangle	rectangle :
Radius:	10	5
Threshold:	None	
Min FWHM:	2.0	2
Max FWHM:	50.0	50 :
Ellipticity:	0.5	
Edge:	0.01	
Max side:	1024	1024
Coordinate Base:	0.0	0.0
Contour Interpolation:	bilinear	bilinear :
Redo Pick		
Readout Settings Cor	ntrols Re	port

Fig. 12: "Settings" tab of Pick plugin.

The "Settings" tab controls aspects of the search within the pick area:

- The "Show candidates" checkbox controls whether all detected sources are marked or not (as shown in the figure below). Additionally, if checked, then all the found objects are added to the pick log table when using the "Report" controls.
- The "Draw type" parameter is used to choose the shape of the pick area to be drawn.
- The "Radius" parameter sets the radius to be used when finding and evaluating bright peaks in the image.
- The "Threshold" parameter is used to set a threshold for peak finding; if set to "None", then a reasonable default value will be chosen.

- The "Min FWHM" and "Max FWHM" parameters can be used to eliminate certain sized objects from being candidates.
- The "Ellipticity" parameter is used to eliminate candidates based on their asymmetry in shape.
- The "Edge" parameter is used to eliminate candidates based on how close to the edge of the cutout they are. *NOTE: currently this works reliably only for non-rotated rectangular shapes.*
- The "Max side" parameter is used to limit the size of the bounding box that can be used in the pick shape. Larger sizes take longer to evaluate.
- The "Coordinate Base" parameter is an offset to apply to located sources. Set to "1" if you want sources pixel locations reported in a FITS-compliant manner and "0" if you prefer 0-based indexing.
- The "Calc center" parameter is used to determine whether the center is calculated from FWHM fitting ("fwhm") or centroiding ("centroid").
- The "FWHM fitting" parameter is used to determine which function is is used for FWHM fitting ("gaussian" or "moffat").
- The "Contour Interpolation" parameter is used to set the interpolation method used in rendering the background image in the "Contour" plot.

The "Redo Pick" button will redo the search operation. It's convenient if you have changed some parameters and want to see the effect based on the current pick area without disturbing it.





Fig. 13: The channel viewer when "Show candidates" is checked.

**User Configuration** 

## Ruler



Ruler is a simple plugin designed to measure distances on an image.

## **Plugin Type: Local**

Ruler is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

Ruler measures distance by calculating a spherical triangulation via WCS mapping of three points defined by a single line drawn on the image. By default, the distance is shown in arcminutes of sky, but using the "Units" control, it can be changed to show degrees or pixel distance instead.

Click and drag to establish a ruler between two points. When you finish the draw operation the ruler is established and the plugin UI will update to show detail about the line, including the endpoint positions and the angle of the line. The units of the angle can be toggled between degrees and radians using the adjacent drop-down box.

To erase the old and make a new ruler, click and drag again. When another line is drawn, it replaces the first one. When the plugin is closed, the graphic overlay is removed. Should you want "sticky rulers", use the Drawing plugin (and choose "Ruler" as the drawing type).

## Editing

To edit an existing ruler, click the radio button in the plugin UI labeled "Edit". If the ruler does not become selected immediately, click on the diagonal connecting the two points. This should establish a bounding box around the ruler and show its control points. Drag within the bounding box to move the ruler or click and drag the endpoints to edit the ruler. The ruler can also be scaled or rotated using those control points.

UI

The units shown for distance can be selected from the drop-down box in the UI. You have a choice of "arcmin", "degrees", or "pixels". The first two require a valid and working WCS in the image.


The endpoint values are shown in the UI, but can additionally be shown in the ruler graphic if the "Show ends" checkbox is toggled. Plumb lines will be shown if the "Show plumb" box is toggled.

#### Buttons

The "Pan to src" button will pan the main image to the origin of the line drawn, while "Pan to dst" will pan to the end. "Pan to ctr" sets the pan position to the center point of the line. These buttons may be useful for close up, zoomed-in work on the image. "Clear" clears the ruler from the image.

**Tips** Open the "Zoom" plugin to precisely see detail of the cursor area (the graphics of the ruler are not shown there, however). The "Pick" plugin can also be used in conjunction with Ruler to identify the central point of an object, when aligning either end of the ruler.

## **MultiDim**



			Row 🗸	id None	f_x pixels	f_y pixels	i_x pixels	i_y pixels	peakValue dn
			0001	458852	207.0	6.0	207	6	57.4831
			0002	458853	1513.0	6.0	1513	6	181.356
			0003	458854	1677.0	12.0	1677	12	3585.14
			0004	458855	1800.0	6.0	1800	6	27.0447
	-	<u> </u>	0005	458856	761.0	14.0	761	14	36.3253
	d		0006	458857	73.0	29.0	73	29	57.0386
			0007	458858	1625.0	34.0	1625	34	9177.11
			0008	458859	1924.0	33.0	1924	33	86.2817
			0009	458860	1554.0	36.0	1554	36	25.873
			0010	458861	242.0	47.0	242	47	103.865
			0011	458862	1801.0	49.0	1801	49	33.575
			0012	458863	1399.0	52.0	1399	52	45.538
			0013	458864	1016.0	52.0	1016	52	28.1596
			0014	458865	161.0	71.0	161	71	54.7149
			0015	458866	870.0	64.0	870	64	27.1998
Synopsis	Command	IMAGE: MultiDim	0016		1381.0	68.0	1381	68	84.89
			0017	458868	1466.0	72.0	1466	72	136.265
	Ins	tructions	0018	458869	1488.0	65.0	1488	65	37.2341
		HDU	0019	458870	1697.0	74.0	1697	74	45.0263
			0020	458871	1509.0	71.0	1509	71	39.0238
	Num HDU	s: 6	0021	458872	307.0	75.0	307	75	318.006
<u> </u>			0022	458873	626.0	79.0	626	79	229.192
4	(4) Bin	TableHDU [1K, 1E,	0023	458874	1248.0	77.0	1248	77	52.6101
	NAXIS (	data cubes)	0024	458875	486.0	78.0	486	78	35.2239
			0025	458876	1332.0	79.0	1332	79	24.5045
	NAXIS		0026	458877	178.0	85.0	178	85	100.501
	NAXIS	2:0	0027	458878	1490.0	83.0	1490	83	24.4113

plugin to navigate HDUs in a FITS file or planes in a 3D cube or higher dimension dataset.

## **Plugin Type: Local**

MultiDim is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

MultiDim is a plugin designed to handle data cubes and multi-HDU FITS files. If you have opened such an image in Ginga, starting this plugin will enable you to browse to other slices of the cube or view other HDUs.

For a data cube, you can save a slice as an image using the "Save Slice" button or create a movie using the "Save Movie" button by entering the "Start" and "End" slice indices. This feature requires mencoder to be installed.

For a FITS table, its data are read in using Astropy table. Column units are displayed right under the main header ("None" if no unit). For masked columns, masked values are replaced with pre-defined fill values.

## **Browsing HDUs**


Use the HDU drop down list in the upper part of the UI to browse and select an HDU to open in the channel.

#### **Navigating Cubes**

Use the controls in the lower part of the UI to select the axis and to step through the planes in that axis.

## **User Configuration**

## Cuts



A plugin for generating a plot of the values along a line or path.

# **Plugin Type: Local**

Cuts is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

# Usage

Cuts plots a simple graph of pixel values vs. index for a line drawn through the image. Multiple cuts can be plotted.

There are four kinds of cuts available: line, path, freepath and beziercurve:

- The "line" cut is a straight line between two points.
- The "path" cut is drawn like an open polygon, with straight segments in-between.
- The "freepath" cut is like a path cut, but drawn using a free-form stroke following the cursor movement.
- The "beziercurve" path is a cubic Bezier curve.

If a new image is added to the channel while the plugin is active, it will update with the new calculated cuts on the new image.

If the "enable slit" setting is enabled, this plugin will also allow slit image functionality (for multidimensional images) via a "Slit" tab. In the tab UI, select one axis from the "Axes" list and draw a line. This will create a 2D image that assumes the first two axes are spatial and index the data along the selected axis. Much like Cuts, you can view the other slit images using the cut selection drop down box.

# **Drawing Cuts**

The "New Cut Type" menu let you choose what kind of cut you are going to draw.

Choose "New Cut" from the "Cut" dropdown menu if you want to draw a new cut. Otherwise, if a particular named cut is selected then that will be replaced by any newly drawn cut.

While drawing a path or beziercurve cut, press 'v' to add a vertex, or 'z' to remove the last vertex added.

## **Keyboard Shortcuts**

While hovering the cursor, press 'h' for a full horizontal cut and 'j' for a full vertical cut.

## **Deleting Cuts**

To delete a cut, select its name from the "Cut" dropdown and click the "Delete" button. To delete all cuts, press "Delete All".

#### **Editing Cuts**

Using the edit canvas function, it is possible to add new vertices to an existing path and to move vertices around. Click the "Edit" radio button to put the canvas in edit mode. If a cut is not automatically selected, you can now select the line, path, or curve by clicking on it, which should enable the control points at the ends or vertices – you can drag these around. To add a new vertex to a path, hover the cursor carefully on the line where you want the new vertex and press 'v'. To get rid of a vertex, hover the cursor over it and press 'z'.

You will notice one extra control point for most objects, which has a center of a different color – this is a movement control point for moving the entire object around the image when in edit mode.

You can also select "Move" to just move a cut unchanged.

#### **Changing Width of Cuts**

The width of 'line' cuts can be changed using the "Width Type" menu:

- "none" indicates a cut of zero radius; i.e., only showing the pixel values along the line
- "x" will plot the sum of values along the X axis orthogonal to the cut.
- "y" will plot the sum of values along the Y axis orthogonal to the cut.
- "perpendicular" will plot the sum of values along an axis perpendicular to the cut.


The "Width radius" controls the width of the orthogonal summation by an amount on either side of the cut - 1 would be 3 pixels, 2 would be 5 pixels, etc.

#### Saving Cuts

Use the "Save" button to save the Cuts plot as as image and data as a Numpy compressed archive.

#### **User Configuration**

## Histogram



Histogram plots a histogram for a

region drawn in the image, or for the entire image.

#### **Plugin Type: Local**

Histogram is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

Usage

Click and drag to define a region within the image that will be used to calculate the histogram. To take the histogram of the full image, click the button in the UI labeled "Full Image".

Note: Depending on the size of the image, calculating the full histogram may take time.

If a new image is selected for the channel, the histogram plot will be recalculated based on the current parameters with the new data.

Unless disabled in the settings file for the histogram plugin, a line of simple statistics for the box is calculated and shown in a line below the plot.

## **UI Controls**

Three radio buttons at the bottom of the UI are used to control the effects of the click/drag action:

- select "Move" to drag the region to a different location
- select "Draw" to draw a new region
- select "Edit" to edit the region

To make a log plot of the histogram, check the "Log Histogram" checkbox. To plot by the full range of values in the image instead of by the range within the cut values, uncheck the "Plot By Cuts" checkbox.

The "NumBins" parameter determines how many bins are used in calculating the histogram. Type a number in the box and press "Enter" to change the default value.

#### **Cut Levels Convenience Controls**

Because a histogram is useful feedback for setting the cut levels, controls are provided in the UI for setting the low and high cut levels in the image, as well as for performing an auto cut levels, according to the auto cut levels settings in the channel preferences.

#### **User Configuration**

# Crosshair

AGE: Crosshair			
	Crosshair		
	Format: coords	* *	
ose Help			

Crosshair is a simple

plugin to draw crosshairs labeled with the position of the cross in pixels coordinates, WCS coordinates, or data value at the cross position.

**Plugin Type: Local** 

Crosshair is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

Select the appropriate type of output in the "Format" drop-down box in the UI: "xy" for pixel coordinates, "coords" for the WCS coordinates, and "value" for the value at the crosshair position.

Then, click and drag to position the crosshair.

# **Overlays**

IMAGE: Overlays	
Opacity	Limits
Opacity:	0.50
Hi limit:	palevioletred =
Lo color:	
Lo limit:	
Redo	200
Redu	
Close	

A plugin for generating color overlays

representing under- and over-exposure in the loaded image.

# Plugin Type: Local

Overlays is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.


Usage

Choose colors from the drop-down menus for the low-limit and/or high-limit ("Lo color" and "Hi color", respectively). Specify the limits for low and high values in the limit boxes ("Lo limit" and "Hi limit", respectively). Set the opacity of the overlays with a value between 0 and 1 in the "Opacity" box. Finally, press the "Redo" button.

The color overlay should show areas below the low limit with a low color and the areas above the high limit in the high color. If you omit a limit (leave the box blank), that color won't be shown in the overlay.

If a new image is selected for the channel, the overlays image will be recalculated based on the current parameters with the new data.

## **WCSAxes**



A plugin for generating WCS axes overlay in the loaded image.


# **Plugin Type: Local**

WCSAxes is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

As long as image as a valid WCS, WCS axes will be displayed. Use plugin GUI or configuration file to customize axes display.

## **TVMark**



Mark points from file (non-interative mode) on an image.

## **Plugin Type: Local**

TVMark is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

This plugin allows non-interactive marking of points of interest by reading in a file containing a table with RA and DEC positions of those points. Any text or FITS table file that can be read by <code>astropy.table</code> is acceptable but user *must* define the column names correctly in the plugin configuration file (see below). An attempt will be made to convert RA and DEC values to degrees. If the unit conversion fails, they will be assumed to be in degrees already.

Alternately, if the file has columns containing the direct pixel locations, you can read these columns instead by unchecking the "Use RADEC" box. Again, the column names must be correctly defined in the plugin configuration file (see below). Pixel values can be 0- or 1-indexed (i.e., whether the first pixel is 0 or 1) and is configurable (see below). This is useful when you want to mark the physical pixels regardless of WCS (e.g., marking hot pixels on a detector). RA and DEC will still be displayed if the image has WCS information but they will not affect the markings.

To mark different groups (e.g., displaying galaxies as green circles and background as cyan crosses, as shown above):

- 1. Select green circle from the drop-down menus. Alternately, enter desired size or width.
- 2. Make sure "Use RADEC" box is checked, if applicable.
- 3. Using "Load Coords" button, load the file containing RA and DEC (or X and Y) positions for galaxies only.
- 4. Repeat Step 1 but now select cyan cross from the drop-down menus.
- 5. Repeat Step 2 but choose the file containing background positions *only*.

Selecting an entry (or multiple entries) from the table listing will highlight the marking(s) on the image. The highlight uses the same shape and color, but a slightly thicker line.

You can also highlight all the markings within a region both on the image and the table listing by drawing a rectangle on the image while this plugin is active.

Pressing the "Hide" button will hide the markings but does not clear the plugin's memory; That is, when you press "Show", the same markings will reappear on the same image. However, pressing "Forget" will clear the markings both from display and memory; That is, you will need to reload your file(s) to recreate the markings.


To redraw the same positions with different marking parameters, press "Forget" and repeat the steps above, as necessary. However, if you simply wish to change the line width (thickness), pressing "Hide" and then "Show" after you entered the new width value will suffice.

If images of very different pointings/dimensions are displayed in the same channel, markings that belong to one image but fall outside another will not appear in the latter.

To create a table that this plugin can read, one can use results from the Pick plugin, in addition to creating a table by hand, using astropy.table, etc.

Used together with TVMask, you can overlay both point sources and masked regions in Ginga.

## **TVMask**



Display masks from file (non-interative mode) on an image.

#### **Plugin Type: Local**

TVMask is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

Usage

This plugin allows non-interactive display of mask by reading in a FITS file, where non-zero is assumed to be masked data.

To display different masks (e.g., some masked as green and some as pink, as shown above):

- 1. Select green from the drop-down menu. Alternately, enter desired alpha value.
- 2. Using "Load Mask" button, load the relevant FITS file.
- 3. Repeat (1) but now select pink from the drop-down menu.
- 4. Repeat (2) but choose another FITS file.
- 5. To display a third mask as pink too, repeat (4) without changing the drop-down menu.

Selecting an entry (or multiple entries) from the table listing will highlight the mask(s) on the image. The highlight uses a pre-defined color and alpha (customizable below).

You can also highlight all the masks within a region both on the image and the table listing by drawing a rectangle on the image while this plugin is active.

Pressing the "Hide" button will hide the masks but does not clear the plugin's memory; That is, when you press "Show", the same masks will reappear on the same image. However, pressing "Forget" will clear the masks both from display and memory; That is, you will need to reload your file(s) to recreate the masks.

To redraw the same masks with different color or alpha, press "Forget" and repeat the steps above, as necessary.

If images of very different pointings/dimensions are displayed in the same channel, masks that belong to one image but fall outside another will not appear in the latter.

To create a mask that this plugin can read, one can use results from the Drawing plugin (press "Create Mask" after drawing and save the mask using SaveImage), in addition to creating a FITS file by hand using astropy.io. fits, etc.

Used together with TVMark, you can overlay both point sources and masked regions in Ginga.

## Blink

Blink	
erval: 1.0	Start Blink Stop Blink
Max: 30.0 Mode: blink images in channel	Min: 0.25
5	

Blink switches

through the images shown in a channel at a rate chosen by the user. Alternatively, it can switch between channels in the main workspace. In both cases, the primary purpose is to compare and contrast the images (within a channel, or across channels) visually within a short timescale – like blinking your eyes.

## Plugin Type: Local or Global

Blink can be invoked either as a local plugin, in which case it cycles through the images in the channel, or as a global

plugin, in which case it cycles through the channels.


Local plugins are started from the "Operations" button, while global plugins are started from the "Plugins" menu.

## Usage

Set the interval between image changes in terms of seconds in the box labeled "Interval". Then, press "Start Blink" to start the timed cycling, and "Stop Blink" to stop the cycling.

You can change the number in "Interval" and press Enter to dynamically change the cycle time while the cycle is running.

## LineProfile



plugin to graph the pixel values along a straight line bisecting a cube.

#### **Plugin Type: Local**

LineProfile is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

#### Usage

Warning: There are no restrictions to what axes can be chosen. As such, the plot can be meaningless.

The LineProfile plugin is used for multidimensional (i.e., 3D or higher) images. It plots the values of the pixels at the current cursor position through the selected axis; or if a region is selected, it plots the mean in each frame. This can be used to create normal spectral line profiles. A marker is placed at the data point of the currently displayed frame.


Displayed X-axis is constructed using CRVAL\*, CDELT\*, CRPIX\*, CTYPE\*, and CUNIT\* keywords from FITS header. If any of the keywords are unavailabled, the axis falls back to NAXIS\* values instead.

Displayed Y-axis is constructed using BTYPE and BUNIT. If they are not available, it simply labels pixel values as "Signal".

To use this plugin:

- 1. Select an axis.
- 2. Pick a point or draw a region using the cursor.
- 3. Use MultiDim to change step values of axes, if applicable.

## **PixTable**



PixTable provides a way to check or monitor the pixel values in a region.

## **Plugin Type: Local**

PixTable is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## **Basic Use**

In the most basic use, simply move the cursor around the channel viewer; an array of pixel values will appear in the "Pixel Values" display in the plugin UI. The center value is highlighted, and this corresponds to the value under the cursor.

You can choose a 3x3, 5x5, 7x7, or 9x9 grid from the left-most combobox control. It may help to adjust the "Font Size" control to prevent having the array values cut off on the sides. You can also enlarge the plugin workspace to see more of the table.

**Note:** The order of the value table shown will not necessarily match to the channel viewer if the images is flipped, transposed, or rotated.

## **Using Marks**

When you set and select a mark, the pixel values will be shown surrounding the mark instead of the cursor. There can be any number of marks, and they are each noted with a numbered "X". Simply change the mark drop down control to select a different mark and see the values around it. The currently selected mark is shown with a different color than the others.

The marks will stay in position even if a new image is loaded and they will show the values for the new image. In this way you can monitor the area around a spot if the image is updating frequently.

If the "Pan to mark" checkbox is selected, then when you select a different mark from the mark control, the channel viewer will pan to that mark. This can be useful to inspect the same spots in several different images, especially when zoomed in tight to the image.

**Note:** If you change the mark control back to "None", then the pixel table will again update as you move the cursor around the viewer.

The "Caption" box can be used to set a text annotation that will be appended to the mark label when the next mark is created. This can be used to label a feature in the image, for example.

## **Deleting Marks**

To delete a mark, select it in the mark control and then press the button marked "Delete". To delete all the marks, press the button marked "Delete All".

### **Moving Marks**

When the "Move" radio button is checked, and a mark is selected, then clicking or dragging anywhere in the image will move the mark to that location and update the pixel table. If no mark is currently selected then a new one will be created and moved.

## **Drawing Marks**

When the "Draw" radio button is checked, then clicking and dragging creates a new mark. The longer the draw, the bigger radius of the "X".

#### **Editing Marks**

When the "Edit" radio button is checked after a mark has been selected then you can drag the control points of the mark to increase the radius of the arms of the X or you can drag the bounding box to move the mark. If the editing control points are not shown, simply click on the center of a mark to enable them.

## **Special Keys**

In "Move" mode the following keys are active: - "n" will place a new mark at the site of the cursor - "m" will move the current mark (if any) to the site of the cursor - "d" will delete the current mark (if any) - "j" will select the previous mark (if any) - "k" will select the next mark (if any)

## **User Configuration**

## Preferences

Make changes to channel settings graphically in the UI.

## **Plugin Type: Local**

Preferences is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

Usage

The Preferences plugin sets the preferences on a per-channel basis. The preferences for a given channel are inherited from the "Image" channel until they are explicitly set and saved using this plugin.

If "Save Settings" is pressed, it will save the settings to the user's home Ginga folder so that when a channel with the same name is created in future Ginga sessions it will obtain the same settings.

### **Color Distribution Preferences**

Color Dis	tribution	
Algorithm:	linear	•
Dist Defaults		

Fig. 14: "Color Distribution" preferences.

The "Color Distribution" preferences control the preferences used for the data value to color index conversion that occurs after cut levels are applied and just before final color mapping is performed. It concerns how the values between the low and high cut levels are distributed to the color and intensity mapping phase.

The "Algorithm" control is used to set the algorithm used for the mapping. Click the control to show the list, or simply scroll the mouse wheel while hovering the cursor over the control. There are eight algorithms available: linear, log, power, sqrt, squared, asinh, sinh, and histeq. The name of each algorithm is indicative of how the data is mapped to the colors in the color map. "linear" is the default.

## **Color Mapping Preferences**

Color M	apping	
Colormap:	ramp	0
Intensity:	ramp	0
Color Defaults		

Fig. 15: "Color Mapping" preferences.

The "Color Mapping" preferences control the preferences used for the color map and intensity map, used during the final phase of the color mapping process. Together with the "Color Distribution" preferences, these control the mapping of data values into a 24-bpp RGB visual representation.

The "Colormap" control selects which color map should be loaded and used. Click the control to show the list, or simply scroll the mouse wheel while hovering the cursor over the control.

The "Intensity" control selects which intensity map should be used with the color map. The intensity map is applied just before the color map, and can be used to change the standard linear scale of values into an inverted scale, logarithmic, etc.

Ginga comes with a good selection of color maps, but should you want more, you can add custom ones or, if matplotlib is installed, you can load all the ones that it has. See "Customizing Ginga" for details.

### Zoom Preferences




Fig. 16: "Zoom" preferences.

The "Zoom" preferences control Ginga's zooming/scaling behavior. Ginga supports two zoom algorithms, chosen using the "Zoom Alg" control:

- The "step" algorithm zooms the image inwards in discrete steps of 1X, 2X, 3X, etc. or outwards in steps of 1/2X, 1/3X, 1/4X, etc. This algorithm results in the least artifacts visually, but is a bit slower to zoom over wide ranges when using a scrolling motion because more "throw" is required to achieve a large zoom change (this is not the case if one uses of the shortcut zoom keys, such as the digit keys).
- The "rate" algorithm zooms the image by advancing the scaling at a rate defined by the value in the "Zoom Rate" box. This rate defaults to the square root of 2. Larger numbers cause larger changes in scale between zoom levels. If you like to zoom your images rapidly, at a small cost in image quality, you would likely want to choose this option.

Note that regardless of which method is chosen for the zoom algorithm, the zoom can be controlled by holding down Ctrl (coarse) or Shift (fine) while scrolling to constrain the zoom rate (assuming the default mouse bindings).

The "Stretch XY" control can be used to stretch one of the axes (X or Y) relative to the other. Select an axis with this control and roll the scroll wheel while hovering over the "Stretch Factor" control to stretch the pixels in the selected axis.

The "Scale X" and "Scale Y" controls offer direct access to the underlying scaling, bypassing the discrete zoom steps. Here, exact values can be typed to scale the image. Conversely, you will see these values change as the image is zoomed.

The "Scale Min" and "Scale Max" controls can be used to place a limit on how much the image can be scaled.

The "Zoom Defaults" button will restore the controls to the Ginga default values.

## **Pan Preferences**

	Panning
Pan X:	0.5
Pan Y:	0.5
Center Image	
Mark Center	

Fig. 17: "Pan" preferences.

The "Pan" preferences control Ginga's panning behavior.

The "Pan X" and "Pan Y" controls offer direct access to set the pan position in the image (the part of the image located at the center of the window) – you can see them change as you pan around the image.

The "Center Image" button sets the pan position to the center of the image, as calculated by halving the dimensions in X and Y.

The "Mark Center" check box, when checked, will cause Ginga to draw a small reticle in the center of the image. This is useful for knowing the pan position and for debugging.

## **Transform Preferences**

	Transform	
🗆 Flip X	🗆 Flip Y	🗌 Swap XY
Rotate:	0.00000000	~
Restore		

Fig. 18: "Transform" preferences.

The "Transform" preferences provide for transforming the view of the image by flipping the view in X or Y, swapping the X and Y axes, or rotating the image in arbitrary amounts.

The "Flip X" and "Flip Y" checkboxes cause the image view to be flipped in the corresponding axis.

The "Swap XY" checkbox causes the image view to be altered by swapping the X and Y axes. This can be combined with "Flip X" and "Flip Y" to rotate the image in 90 degree increments. These views will render more quickly than arbitrary rotations using the "Rotate" control.

The "Rotate" control will rotate the image view the specified amount. The value should be specified in degrees. "Rotate" can be specified in conjunction with flipping and swapping.

The "Restore" button will restore the view to the default view, which is unflipped, unswapped, and unrotated. **Auto Cuts Preferences** 

		Au	to Cuts
Cut Low:	: 0		
Cut High:	: 0		
			Cut Levels
Auto Method:	zscale	•	Auto Levels
contrast:	0.25		
num_points:	1000		

Fig. 19: "Auto Cuts" preferences.

The "Auto Cuts" preferences control the calculation of cut levels for the view when the auto cut levels button or key is pressed, or when loading a new image with auto cuts enabled. You can also set the cut levels manually from here.

The "Cut Low" and "Cut High" fields can be used to manually specify lower and upper cut levels. Pressing "Cut Levels" will set the levels to these values manually. If a value is missing, it is assumed to default to the whatever the current value is.

Pressing "Auto Levels" will calculate the levels according to an algorithm. The "Auto Method" control is used to choose which auto cuts algorithm used: "minmax" (minimum maximum values), "median" (based on median filtering), "histogram" (based on an image histogram), "stddev" (based on the standard deviation of pixel values), or "zscale" (based on the ZSCALE algorithm popularized by IRAF). As the algorithm is changed, the boxes under it may also change to allow changes to parameters particular to each algorithm.

## WCS Preferences

W	S	
WCS Coords:	icrs	0
WCS Display:	sexagesimal	•

Fig. 20: "WCS" preferences.

The "WCS" preferences control the display preferences for the World Coordinate System (WCS) calculations used to report the cursor position in the image.

The "WCS Coords" control is used to select the coordinate system in which to display the result.

The "WCS Display" control is used to select a sexagesimal (H:M:S) readout or a decimal degrees readout.

## **New Image Preferences**

The "New Images" preferences determine how Ginga reacts when a new image is loaded into the channel. This includes when an older image is revisited by clicking on its thumbnail in the Thumbs plugin pane.

New Ir	nages
Cut New:	override 🛛 🗘
Zoom New:	off 🛛
Center New	✓ Follow New
Raise New	Create thumbnail

Fig. 21: "New Image" preferences.

The "Cut New" setting controls whether an automatic cut-level calculation should be performed on the new image, or whether the currently set cut levels should be applied. The possible settings are:

- "on": calculate a new cut levels always;
- "override": calculate a new cut levels until the user overrides it by manually setting a cut levels, then turn "off"; or
- "off": always use the currently set cut levels.

**Tip:** The "override" setting is provided for the convenience of having automatic cut levels, while preventing a manually set cuts from being overridden when a new image is ingested. When typed in the image window, the semicolon key can be used to toggle the mode back to override (from "off"), while colon will set the preference to "on". The Info panel shows the state of this setting.

The "Zoom New" setting controls whether a newly visited image should be zoomed to fit the window. There are three possible values: on, override, and off:

- "on": the new image is always zoomed to fit;
- "override": images are automatically fitted until the zoom level is changed manually, then the mode automatically changes to "off", or
- "off": always use the currently set zoom levels.

**Tip:** The "override" setting is provided for the convenience of having an automatic zoom, while preventing a manually set zoom level from being overridden when a new image is ingested. When typed in the image window, the apostrophe (a.k.a. "single quote") key can be used to toggle the mode back to "override" (from "off"), while quote (a.k.a. double quote) will set the preference to "on". The global plugin Info panel shows the state of this setting.

The "Center New" box, if checked, will cause newly visited images to always have the pan position reset to the center of the image. If unchecked, the pan position is unchanged from the previous image.

The "Follow New" setting is used to control whether Ginga will change the display if a new image is loaded into the channel. If unchecked, the image is loaded (as seen, for example, by its appearance in the Thumbs tab), but the display will not change to the new image. This setting is useful in cases where new images are being loaded by some automated means into a channel and the user wishes to study the current image without being interrupted.

The "Raise New" setting controls whether Ginga will raise the tab of a channel when an image is loaded into that channel. If unchecked, then Ginga will not raise the tab when an image is loaded into that particular channel.

The "Create Thumbnail" setting controls whether Ginga will create a thumbnail for images loaded into that channel. In cases where many images are being loaded into a channel frequently (e.g., a low frequency video feed), it may be undesirable to create thumbnails for all of them.

### **General Preferences**

The "Num Images" setting specifies how many images can be retained in buffers in this channel before being ejected. A value of zero (0) means unlimited–images will never be ejected. If an image was loaded from some accessible storage and it is ejected, it will automatically be reloaded if the image is revisited by navigating the channel.

The "Sort Order" setting determines whether images are sorted in the channel alphabetically by name or by the time when they were loaded. This principally affects the order in which images are cycled when using the up/down "arrow" keys or buttons, and not necessarily how they are displayed in plugins like "Contents" or "Thumbs" (which generally have their own setting preference for ordering).

The "Use scrollbars" check box controls whether the channel viewer will show scroll bars around the edge of the viewer frame.

### **Remember Preferences**

When an image is loaded, a profile is created and attached to the image metadata in the channel. These profiles are continuously updated with viewer state as the image is manipulated. The "Remember" preferences control which parts of these profiles are restored to the viewer state when the image is navigated to in the channel:

- "Restore Scale" will restore the zoom (scale) level
- "Restore Pan" will restore the pan position
- "Restore Transform" will restore any flip or swap axes transforms
- "Restore Rotation" will restore any rotation of the image
- "Restore Cuts" will restore any cut levels for the image
- "Restore Scale" will restore any coloring adjustments made (including color map, color distribution, contrast/stretch, etc.)

## Catalogs

A plugin for plotting object locations from a catalog on an image.

## **Plugin Type: Local**

Catalogs is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

#### Usage

Before Catalogs can be used, you need to define at least one catalog or image server to be queried in ginga\_config.py. Here is an example for defining three cone search catalogs for guide stars:

```
def pre_gui_config(ginga):
    from ginga.util.catalog import AstroPyCatalogServer
    # Add Cone Search services
    catalogs = [
        ('The HST Guide Star Catalog, Version 1.2 (Lasker+ 1996) 1',
        'GSC_1.2'),
        ('The PMM USNO-A1.0 Catalogue (Monet 1997) 1', 'USNO_A1'),
        ('The USNO-A2.0 Catalogue (Monet+ 1998) 1', 'USNO_A2'),
    ]
    bank = ginga.get_ServerBank()
    for longname, shortname in catalogs:
```

(continues on next page)


(continued from previous page)

```
obj = AstroPyCatalogServer(
        ginga.logger, longname, shortname, '', shortname)
        bank.addCatalogServer(obj)
def post_gui_config(ginga):
    pass
```

Then, start Ginga and then start the Catalogs local plugin from the channel you want to perform searchs on. You will see the catalogs listed in a drop-down menu on the plugin GUI.

Draw a shape on the displayed image and adjust search parameters as desired. When you are ready, press on the button to perform the search. When search results are available, they will be displayed on the image and also listed in a table on the plugin GUI. You can click on either the table or the image to highlight selection.

## Mosaic



Plugin to create an image mosaic by constructing a composite image.

## **Plugin Type: Local**

Mosaic is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

Usage

### Warning: This can be very memory intensive.

This plugin is used to automatically build a mosaic image in the channel using images provided by the user (e.g., using FBrowser). The position of an image on the mosaic is determined by its WCS without distortion correction. This is meant as a quick-look tool, not a replacement for image drizzling that takes account of image distortion, etc. The mosaic only exists in memory but you can save it out to a FITS file using SaveImage.


When a mosaic falls out of memory, it is no longer accessible in Ginga. To avoid this, you must configure your session such that your Ginga data cache is sufficiently large (see "Customizing Ginga" in the manual).

To create a new mosaic, set the FOV and drag files onto the display window. Images must have a working WCS. The first image's WCS will be used to orient the other tiles.

### Difference from `Collage` plugin

- Allocates a single large array to hold all the mosaic contents
- Slower to build, but can be quicker to manipulate large resultant images
- Can save the mosaic as a new data file
- Fills in values between tiles with a fill value (can be NaN)

## Collage



Plugin to create an image mosaic via the collage method.

## **Plugin Type: Local**

Collage is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

This plugin is used to automatically create a mosaic collage in the channel viewer using images provided by the user. The position of an image on the collage is determined by its WCS without distortion correction. This is meant as a quick-look tool, not a replacement for image drizzling that takes account of image distortion, etc.

The collage only exists as a plot on the Ginga canvas. No new single image is actually built (if you want that, see the "Mosaic" plugin). Some plugins that expect to operate on single images may not work correctly with a collage.

To create a new collage, click the "New Collage" button and drag files onto the display window (e.g. files can be dragged from the FBrowser plugin). Images must have a working WCS. The first image processed will be loaded and its WCS will be used to orient the other tiles. You can add new images to an existing collage simply by dragging additional files.

## Controls

Check the "Collage HDUs" button to have Collage attempt to plot all the image HDUs in a dragged file instead of just the first found one.

Check "Label Images" to have the plugin draw the name of each image over each plotted tile.

If "Match bg" is checked, the background of each tile is adjusted relative to the median of the first tile plotted (a kind of rough smoothing).

The "Num Threads" box assigns how many threads will be used from the thread pool to load the data. Using several threads will usually speed up loading of many files.

### Difference from `Mosaic` plugin

- Doesn't allocate a large array to hold all the mosaic contents
- No need to specify output FOV or worry about it
- Can be quicker to show result (depends a bit on constituent images)
- Some plugins will not work correctly with a collage, or will be slower
- Cannot save the collage as a data file (although you can use "ScreenShot")

## Drawing

A plugin for drawing canvas forms (overlaid graphics).

## **Plugin Type: Local**

Drawing is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

#### Usage

This plugin can be used to draw many different shapes on the image display. When it is in "draw" mode, select a shape from the drop-down menu, adjust the shape's parameters (if needed), and draw on the image by using left mouse button. You can choose to draw in pixel or WCS space.

To move or edit an existing shape, set the plugin on "edit" or "move" mode, respectively.

To save the drawn shape(s) as mask image, click the "Create Mask" button and you will see a new mask image created in Ginga. Then, use SaveImage plugin to save it out as single-extension FITS. Note that the mask will take the size of the displayed image. Therefore, to create masks for different image dimensions, you need to repeat the steps multiple times.

## **FBrowser**

A plugin for browsing the local filesystem and loading files.

## Plugin Type: Global or Local

FBrowser is a hybrid global/local plugin, which means it can be invoked in either fashion. If invoked as a local plugin then it is associated with a channel, and an instance can be opened for each channel. It can also be opened as a global plugin.

## Usage

Navigate the directory tree until you come to the location files you want to load. You can double click a file to load it into the associated channel, or drag a file into a channel viewer window to load it into any channel viewer.

Multiple files can be selected by holding down Ctrl (Command on Mac), or Shift-clicking to select a contiguous range of files.

You may also enter full path to the desired image(s) in the text box such as /my/path/to/image.fits, /my/path/to/image.fits[ext], or /my/path/to/image\*.fits[extname,\*].

Because it is a local plugin, FBrowser will remember its last directory if closed and then restarted.

## Compose

A plugin for composing RGB images from constituent monochrome images.

## **Plugin Type: Local**

Compose is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

#### Usage

Start the Compose plugin from the "Operation->RGB" (below) or "Plugins->RGB" (above) menu. The tab should show up under the "Dialogs" tab in the viewer to the right as "IMAGE:Compose".

- 1. Select the kind of composition you want to make from the "Compose Type" drop down: "RGB" for composing three monochrome images into a color image, "Alpha" to compose a series of images as layers with different alpha values for each layer.
- 2. Press "New Image" to start composing a new image.

#### \*For RGB composition\*

1. Drag your three constituent images that will make up the R, G, and B planes to the "Preview" window – drag them in the order R (red), G (green), and B (blue). Alternatively, you can load the images into the channel viewer one by one and after each one pressing "Insert from Channel" (similarly, do these in the order of R, G, and B).

In the plugin GUI, the R, G, and B images should show up as three slider controls in the "Layers" area of the plugin, and the Preview should show a low resolution version of how the composite image looks with the sliders set.

- 2. Play with the alpha levels of each layer using the sliders in the Compose plugin; as you adjust a slider the preview image should update.
- 3. When you see something you like, you can save it to a file using the "Save As" button (use "jpeg" or "png" as the file extension), or insert it into the channel using the "Save to Channel" button.

#### \*For Alpha composition\*

For Alpha-type composition the images are just combined in the order shown in the stack, with Layer 0 being the bottom layer, and successive layers stacked on top. Each layer's alpha level is adjustible by a slider in the same manner as discussed above.




Fig. 22: Composing an RGB Image.

- 1. Drag your N constituent images that will make up the layers to the "Preview" window, or load the images into the channel viewer one by one and after each one pressing "Insert from Channel" (the first image will be at the bottom of the stack–layer 0).
- 2. Play with the alpha levels of each layer using the sliders in the Compose plugin; as you adjust a slider the preview image should update.
- 3. When you see something you like, you can save it to a file using the "Save As" button (use "fits" as the file extension), or insert it into the channel using the "Save to Channel" button.

## \*General Notes\*

• The preview window is just a ginga widget, so all the usual bindings apply; you can set color maps, cut levels, etc. with the mouse and key bindings.




Fig. 23: Alpha-composing an image.

## **PlotTable**

			IMAGE: PlotTable	
Row 🔻	WAVELENGTH ANGSTROMS	FLUX FLAM	Plot	
0001	900.4520263671875			
	901.354	1.690418e-17	1e-8	
	902.258	1.7957699e-17		
	903.163	1.8396666e-17	0.8	
0005	904.068	1.8819668e-17	Î Î Î Î Î Î Î Î Î Î Î Î Î Î Î Î Î Î Î	
0006	904.974	1.9338445e-17	ĨĨÎ Ă     <b>          </b>	
0007	905.882	1.9865204e-17	(W J 0.6 	
0008	906.79	2.036802e-17		
0009	907.699	2.08868e-17		
0010	908.609	2.1413559e-17	E 0.4	
0011	909.52	2.1948298e-17		
0012	910.431	2.2506982e-17	0.2	
0013	911.344	2.3105572e-17	0.2	
0014	912.258	2.3919655e-17	40 <sup>60</sup> 40 <sup>80</sup> 41 <sup>00</sup> 41 <sup>20</sup> 41 <sup>40</sup>	
0015	913.172	2.6170352e-17	as as as as as	
0016	914.088	4.7544006e-17	WAVELENGTH (ANGSTROMS)	
0017	915.004	3.6681593e-16		
0018	915.921	2.3728105e-15		
0019	916.84	6.90693e-15	X: WAVELENGTH 👻	F
	917.759	1.1620627e-14		
0021	918.679	1.549949e-14	Y: FLUX 👻	
	919.6	1.9561921e-14	Log X Log Y ✓ Show Marker	
	920.522	2.2419188e-14		
	921.445	2.6457676e-14	X Low: 4050	
	922.368	2.926706e-14	X High: 4150	
	923.293	3.155766e-14	4150	
	924.219	4.6394712e-14	Y Low: 2e-9	
	925.145	4.7081096e-14		
4		)	Y High: 9e-9	
0	0 0	0 0	Save	L
	0 0	0 0		-
Value: Image	Operation Zoom	Header IMAGE:	Close Help	

A plugin to display basic plot for any two selected columns in a table.

## **Plugin Type: Local**

PlotTable is a local plugin, which means it is associated with a channel. An instance can be opened for each channel.

## Usage

PlotTable is a plugin designed to plot any two selected columns for a given FITS table HDU (can be accessed via MultiDim). For masked columns, masked data is not shown (even if only one of the (X, Y) pair is masked). It is meant as a way to quickly look at table data and not for detailed scientific analysis.

## Pipeline

Simple data reduction pipeline plugin for Ginga.

Note: This plugin is available but not loaded into Ginga reference viewer by default because it is experimental.

## **Plugin Type: Local**

Pipeline is a local plugin, which means it is associated with a channel. An instance can be opened for each channel. Usage

# IMAGE: Crosshair IMAGE: ScreenShot Image Help Screenshot α:20:00:03.826, δ:+22:48:38.194 α:20:00:03.826, δ:+22:48:38.194 Type: png Snap Clear Center Fit Save File Folder: /tmp Name: rhiophan Save $\alpha$ : 20:00:03.604 $\delta$ : +22:48:34.985 X: 1014.394 Y: 2133.089 Value: 443 IMAGE. ScreenShot Image : Operation Crosshai Close Help

## ScreenShot

Capture PNG or JPEG images of the channel viewer image.

Usage

- 1. Select the RGB graphics type for the snap from the "Type" combo box.
- 2. Press "Snap" when you have the channel image the way you want to capture it.

A copy of the RGB image will be loaded into the ScreenShot viewer. You can pan and zoom within the ScreenShot viewer like a normal Ginga viewer to examine detail (e.g., see the magnified difference between JPEG and PNG formats).

- 3. Repeat (1) and (2) until you have the image you want.
- 4. Enter a valid path for a new file into the "Folder" text box.

- 5. Enter a valid name for a new file into the "Name" text box. There is no need to add the file extension; it will be added, if needed.
- 6. Press the "Save" button. The file will be saved where you specified.

Notes

- PNG offers less artifacts for overlaid graphics, but files are larger than JPEG.
- The "Center" button will center the snap image; "Fit" will set the zoom to fit it to the window; and "Clear" will clear the image. Press "Full" to zoom to 100% pixels (1:1 scaling).
- The "Screen size" checkbox (checked by default) will save the image at exactly the size of the channel viewer window. To save at a different size, uncheck this box, and set the size via the "Width" and "Height" boxes.
- The "Lock aspect" feature only works if "Screen size" is unchecked; if enabled, then changing width or height will alter the other parameter in order to maintain the aspect ratio shown in the "Aspect" box.

# 4.5 Customizing Ginga

One of the primary guiding concepts behind the Ginga project is to provide convenient ways to build custom viewers. The reference viewer embodies this concept through the use of a flexible layout engine and the use of plugins to implement all the major user interface features. By modifying or replacing the layout and adding, subclassing or removing plugins you can completely change the look, feel and operation of the reference viewer.

This chapter explains how you can customize the Ginga reference viewer in various ways, as a user or a developer.

# 4.5.1 Configuration Options

Ginga examines a configuration directory on startup to check for any configuration files or customization of the default behavior.

Note: The configuration area is determined first by examining the command line option --basedir. If that is not set, then the environment variable GINGA\_HOME is checked. If that is not set, then \$HOME/.ginga (Mac OS X, Linux) or \$HOMEDRIVE:\$HOMEPATH\\.ginga (Windows) will be used.

Examples of the types of configuration files with comments describing the effects of the parameters can be found in .../ginga/examples/configs.

The config files that end in .cfg use a stripped down Pythonic format consisting of comments, blank lines and keyword = value pairs, where values are specified using Python literal syntax.

## **General Config Files**

There is general top-level configuration file general.cfg in the configuration area. You can find an example in the examples area described above.

## **Binding Config File**

One configuration file that many users will be interested in is the one controlling how keyboard and mouse/touch bindings are assigned. This is handled by the configuration file bindings.cfg. Several examples are stored in .../ginga/examples/bindings, including an example for users familiar with the ds9 mouse controls, and an example for users using a touchpad without a mouse (pinch zoom and scroll panning). Simply copy the appropriate file to your Ginga settings area as bindings.cfg.

## **Plugin Config Files**

Many of the plugins have their own configuration file, with preferences that are only changed via that file. You can copy an example configuration file to your Ginga settings area and change the settings to your liking.

Here is an example of a plugin configuration file for the Ruler plugin:

```
#
# Ruler plugin preferences file
# Place this in file under ~/.ginga with the name "plugin Ruler.cfg"
# Show plumb lines or not
show_plumb = True
# Show end values or not (end values are shown in the UI boxes,
# regardless)
show_ends = True
# Color for a drawn ruler
rule_color = 'green'
# Color used when drawing
draw_color = 'cyan'
# Units of distance. Choices are 'arcmin', 'degrees' or 'pixels';
# the first two require a working WCS in the image.
units = 'arcmin'
# The unit for showing the angle of the ruler.
# Choices are 'degrees' or 'radians'
angle_unit = 'degrees'
```

Usually it is sufficient to simply close the plugin and open it again to pick up any settings changes, but some changes may require a viewer restart to take effect.

## **Channel Config Files**

Channels also use configuration files to store many different settings for the channel viewer windows. When a channel is created, the reference viewer looks to see if there is a configuration file for that channel in the configuration area; if so, the settings therein are used to configure it. If not, the settings for the generic startup channel "Image" are used to configure the new channel. The "Preferences" plugin can be used to set many of the channel settings. If you set these for the "Image" channel and use the "Save" button, other channels will inherit them. You can also manually copy the example file from .../ginga/examples/configs/channel\_Image.cfg to your configuration area and edit it if you prefer.

# 4.5.2 Customizing the Layout

Ginga has a flexible table-driven layout scheme for dynamically creating workspaces and mapping the available plugins to workspaces. This layout can be specified with a Python structure (layout) in the configuration area. If there is no file initially, Ginga will use the built in default layout. Ginga will will update its window size, position and some layout information to the layout file when the program is closed, creating a new custom layout. Upon a subsequent startup Ginga will attempt to restore the window to the saved configuration.

**Note:** The name of the layout file is set in the general configuration file (general.cfg) as the value for layout\_file. Set it to "layout\_json" if you prefer to use the JSON format or "layout" if you prefer to use the Python format (the default).

**Note:** If you don't want Ginga to remember your changes to the window size or position, you can add the option save\_layout = False to your general configuration file. Ginga will still read the layout from the file (if it exists-otherwise it will use the default, built-in layout), but will not update it when closing.

**Note:** Invoking the program with the --norestore option prevents it from reading the saved layout file, and forces use of the internal default layout table. This may be needed in some cases when the layout changes in an incompatible way between when the program was last stopped and when it was started again.

## Format of the Layout Table

The table consists of a list containing nested lists. Each list represents a container or a non-container endpoint, and has the following format:

[type config-dict optional-content0 ... optional-contentN]

The first item in a list indicates the type of the container or object to be constructed. The following types are available:

- seq: defines a sequence of top-level windows to be created
- hpanel: a horizontal panel of containers, with handles to size them
- vpanel: a vertical panel of containers, with handles to size them
- hbox: a horizontal panel of containers of fixed size
- vbox: a vertical panel of containers of fixed size
- ws: a workspace that allows a plugin or a channel viewer to be loaded into it. A workspace can be configured in four ways: as a tabbed notebook (wstype="tabs"), as a stack (wstype="stack"), as an MDI (Multiple Document Interface, wstype="mdi") or a grid (wstype="grid").

In every case the second item in the sublist is a dictionary that provides some optional parameters that modify the characteristics of the widget. If there is no need to override the default parameters the dictionary can simply be empty. All types of containers honor the following parameters in this dict:

- width: can specify a desired width in pixels for the container.
- height: can specify a desired height in pixels for the container.
- name: specifies a mapping of a name to the created container widget. The name is important especially for workspaces, as they may be referred to as an output destination when registering plugins.

The optional third and following items in a list are specifications for nested content. The format for nested content depends on the type of the container:

- seq, hpanel and vpanel types expect the nested content items to be lists, as described above.
- hbox and vbox content items can be lists (as described above) or dict s. A vbox dict should have a row value and optionally a stretch value; an hbox dict should have a col value and optionally a stretch value. The row and col values should be lists as described above.
- The ws (workspace) type takes one optional content item, which should be a sublist containing 2-item lists (or tuples) with the format (name, content), where content is a list as described above. The name is used to identify each content item in the way appropriate for the workspace type, whether that is a notebook tab, MDI window titlebar, etc.

Here is the standard layout (Python format), as an example:

```
['seq',
{},
['vbox',
 {'height': 700, 'name': 'top', 'width': 1400},
 {'row': ['hbox', {'name': 'menu'}], 'stretch': 0},
 {'row': ['hpanel',
           {'name': 'hpnl'},
           ['ws',
            {'group': 2,
             'height': -1,
             'name': 'left',
             'width': 300,
             'wstype': 'tabs'},
            [('Info',
              ['vpanel',
               {},
               ['ws',
                {'group': 3,
                 'height': 250,
                 'name': 'uleft',
                 'wstype': 'stack'}],
               ['ws',
                {'group': 3,
                 'height': 330,
                 'name': 'lleft',
                 'wstype': 'tabs'}]])]],
           ['vbox',
            {'name': 'main', 'width': 600},
            {'row': ['ws',
                     {'default': True,
                      'group': 1,
                      'name': 'channels',
                      'use_toolbar': True,
                      'wstype': 'tabs'}],
             'stretch': 1},
            {'row': ['ws', {'group': 99, 'name': 'cbar', 'wstype': 'stack'}],
             'stretch': 0},
            {'row': ['ws', {'group': 99, 'name': 'readout', 'wstype': 'stack'}],
             'stretch': 0},
            {'row': ['ws',
                     {'group': 99, 'name': 'operations', 'wstype': 'stack'}],
             'stretch': 0}],
           ['ws',
```

(continues on next page)

(continued from previous page)

In the above example, we define a top-level window consisting of a vbox (named "top") with 4 layers: a hbox ("menu"), hpanel ("hpnl"), a workspace ("toolbar") and another hbox ("status"). The main horizontal panel ("hpnl") has three containers: a workspace ("left"), a vbox ("main") and a workspace ("right"). The "left" workspace is pre-populated with an "Info" tab containing a vertical panel of two workspaces: "uleft" and "lleft" (upper and lower left). The "right" workspace is pre-populated with a "Dialogs" tab containing an empty workspace. The "main" vbox is configured with four rows of workspaces: "channels", "cbar", "readout" and "operations".

**Note:** The workspace that has as a configuration option default: True (in this example, "channels") will be used as the default workspace where new channels should be created.

# 4.5.3 Customizing the set of plugins

In the configuration directory, the presence of a file plugins.json will override the built-in configuration of plugins. The file format is a JSON array containing JSON objects, each of which configures a plugin. Example:

```
{
    "__bunch__": true,
    "module": "Info",
    "tab": "Synopsis",
    "workspace": "lleft",
    "start": true,
    "hidden": true,
    "category": "System",
    "menu": "Info [G]",
    "ptype": "global"
},
...
]
```

[

The keys for each object are defined as follows:

- \_\_bunch\_\_: should be present and set to true to force deserialization to a Bunch.
- module: The name of the module in the **\$PYTHONPATH** containing the plugin.
- class: if present, indicates the name of the class within the module that denotes the plugin (if not present the class is assumed to be named identically to the module).
- tab: the name that the plugin should appear as when opened in a workspace (usually as a tab, but it depends on the type of workspace). Often the same name as the class, but can be different. If not present, defaults to the class or module name of the plugin.

- workspace: the name of the workspace defined in the layout file (or default layout) where the plugin should be started (see section below on workspace customization).
- start: true if the module is of the global type and should be started at program startup. Defaults to false.
- hidden: true if the plugin should be hidden from the "Operation" and "Plugins" menus. Often paired with hidden being true for plugins that are considered to be a necessary part of continuous operation from program startup to shutdown. Defaults to false.
- category: an arbitrary organizational name under which plugins are organized in the Operation and Plugins menus.
- menu: a name for how the plugin should appear under the category in the menu structure. The convention is to append "[G]" if it is a global plugin.
- ptype: either "local" or "global", depending on whether the plugin is a local or global one.
- optray: to prevent a control icon from appearing in the Operations plugin manager tray specify false. The default for non-hidden plugins is true and for hidden plugins false.
- enabled: false to disable the plugin from being loaded.

See the standard set of plugins in .../ginga/examples/layouts/standard/plugins.json

## **Custom plugin directory**

If there is a plugins directory in the configuration area, it is added to the PYTHONPATH for the purpose of loading plugins. You can put plugin modules in this directory, and then add entries to the plugins.json file described above to add new, custom plugins.

# 4.5.4 Customizing the Reference Viewer (with Python) During Initialization

For the ultimate flexibility, the reference viewer can be customized during viewer initialization using a Python module called ginga\_config, which can be anywhere in the user's Python import path, including in the Ginga configuration folder described above.

Specifically, this file will be imported and two methods will be run if defined: pre\_gui\_config (ginga\_shell) and post\_gui\_config (ginga\_shell). The parameter to each function is the main viewer shell. These functions can be used to define a different viewer layout, add or remove plugins, add menu entries, add custom image or star catalogs, etc. We will refer back to these functions in the sections below.

## Workspace configuration

You can create a layout table (as described above in "Customizing the Workspace") as a Python data structure, and then replace the default layout table in the pre\_gui\_config() method described above:

If done in the pre\_gui\_config() method (as shown) the new layout will be the one that is used when the GUI is constructed. See the default layout in ~ginga.rv.main as an example.

#### **Start Plugins and Create Channels**

You can create channels and start plugins using the post\_gui\_config() method.

A plugin can be started automatically in post\_gui\_config() using the start\_global\_plugin() or start\_local\_plugin() methods, as appropriate:

```
def post_gui_config(ginga_shell):
    # Auto start global plugins
    ginga_shell.start_global_plugin('Zoom')
    ginga_shell.start_global_plugin('Header')
    # Auto start local plugin
    ginga_shell.add_channel('Image')
    ginga_shell.start_local_plugin('Image', 'Histogram', None)
```

Alternately, you can also start plugins via the command line interface using --plugins and -modules for local and global plugins, respectively. To load multiple plugins at once, use a comma-separated list. For example:

ginga --plugins=MyLocalPlugin,Imexam --modules=MyGlobalPlugin

## **Adding Plugins**

A plugin can be added to the reference viewer in pre\_gui\_config() using the add\_plugin() method with a specification ("spec") for the plugin:

The above call would try to load a local plugin called "DQCheck" from a module called "DQCheck". When invoked from the Operations menu it would occupy a spot in the "dialogs" workspace (see layout discussion above).

#### **Disabling Plugins**

Both local and global plugins can be disabled (thus, not shown in the reference viewer) using the --disable-plugins option in the command line interface. To remove multiple plugins at once, use a comma-separated list. For example:

ginga --disable-plugins=Zoom,Compose

Alternately, plugins can also be disabled via general.cfg configuration file. For example:

disable\_plugins = "Zoom, Compose"

Finally, if you are using a custom "plugins.json" file as described above, you can simply set the enabled attribute to False in the JSON object for that plugin in the file.

Some plugins, like Operations, when disabled, may result in inconvenient GUI experience.

# 4.5.5 Making a Custom Startup Script

You can make a custom startup script to make the same reference viewer configuration available without relying on a custom set of startup files or the ginga\_config module. To do this we make use of the *main* module:

```
import sys
from argparse import ArgumentParser
from ginga.rv.main import ReferenceViewer
# define your custom layout
my_layout = [ ... ]
# define your custom plugin list
plugins = [ ... ]
if __name__ == "__main__":
   viewer = ReferenceViewer(layout=my_layout)
    # add plugins
   for spec in plugins:
       viewer.add_plugin(spec)
   argprs = ArgumentParser(description="Run my custom viewer.")
   viewer.add_default_options(argprs)
    (options, args) = argprs.parse_known_args(sys_argv[1:])
   viewer.main(options, args)
```

## CHAPTER

# **DEVELOPER'S MANUAL**

This section provides some resources for developers interested in using Ginga as a visualization solution for their own software.

# 5.1 Image Data Wrappers

The image viewer can load data in a number of formats, but all formats are wrapped with a class that corresponds to the *model* part of the model-view-controller design used by Ginga. These wrappers make the data accessible in a common interface for the image viewer. The most common wrappers are AstroImage and RGBImage, for single band (i.e. "monchromatic") and multi-band (i.e. "RGB") data, respectively.

## 5.1.1 Astrolmage

An AstroImage combines image data with metadata (including keywords) and optionally, world coordinate information.

Data can be loaded in a number of ways. For the following examples, assume that we created a wrapper object via:

```
>>> from ginga.AstroImage import AstroImage
>>> img = AstroImage()
```

**Note:** Ginga provides extensive logging throughout the code, so if you are using a Python logger you can pass it to the constructor to have it log extra information about errors when methods on the image object are being used. Assuming you had a logger configured as logger you would pass it like so:

```
>>> img = AstroImage(logger=logger)
```

Once you have an object, you can load data directly contained in a numpy.ndarray:

```
>>> import numpy as np
>>> data = np.random.randint(0, 10000, (2000, 3000), dtype=np.uint)
>>> img.load_data(data)
```

Note: if you want to provide metadata (e.g. a separate set of FITS-type keywords) you can add it:

```
>>> img.update_keywords(kw_dict)
```

From an astropy.io.fits.HDU:

```
>>> from astropy.io import fits
>>> with fits.open("/path/to/image.fits") as fits_f:
>>> img.load_hdu(fits_f[0])
```

From an astropy.nddata.NDData (or subclass, like CCDData):

>>> img.load\_nddata(ndd\_obj)

Files are best loaded from the appropriate file format loader module. For a FITS file:

```
>>> from ginga.util import io_fits
>>> img = io_fits.load_file("/path/to/image.fits")
```

Or, e.g. to choose a particular HDU:

```
>>> from ginga.util import io_fits
>>> img = io_fits.load_file("/path/to/image.fits[SCI]")
```

# 5.1.2 RGBImage

The RGBImage class is used to store conventional type 3 or 4-band RGB images.

```
>>> from ginga.RGBImage import RGBImage
>>> img = RGBImage()
```

**Note:** RGBImage constructor also supports the logger keyword parameter described above:

>>> img = RGBImage(logger=logger)

RGB images support the load\_data method (note the shape and type of the array):

```
>>> data = np.random.randint(0, 256, (1000, 1000, 3), dtype=np.uint8)
>>> img.load_data(data)
```

Files can also be loaded from standard RGB formats (PNG, JPEG, etc) using the io\_rgb module:

```
>>> from ginga.util import io_rgb
>>> img = io_rgb.load_file("/path/to/image.jpg")
```

# 5.2 Ginga Image Viewer Operations

This chapter describes the operations supported by the basic Ginga image viewer and how to access them programatically.

# 5.2.1 Manipulating the view programatically

The sections below describe how to manipulate the view programatically. For all of these API examples we assume the viewer object is contained in variable v. One way to create one:

```
>>> from ginga import toolkit
>>> toolkit.use('qt5')
>>> from ginga.gw import Viewers
>>> from ginga.misc import log
>>> logger = log.get_logger("viewer1", log_stderr=True, level=40)
>>> v = Viewers.CanvasView(logger=logger)
```

Many of the API calls simply set a value in the viewer's settings object; if so, we note the associated keyword for that setting.

## 5.2.2 Loading the Viewer

The image viewer can load data in a number of formats, but all formats are wrapped with a class that corresponds to the *model* part of the model-view-controller design used by Ginga. For more information on creating an image wrapper object, see *Image Data Wrappers*.

Once you have successfully loaded an image wrapper, you can set it into the image viewer:

```
>>> v.set_image(img)
```

## 5.2.3 Scaling

In Ginge lexicon, "scaling" is setting a precise scale factor for pixels. For example a scale factor of 2.0 means that two pixels are shown in the viewer for every one pixel of data.

Ginga allows different scale factors for the X and Y axes.

Set a precise scale for X and Y:

>>> v.set\_scale((0.5, 0.5))

Note: Corresponds to the viewer setting scale.

Get the scale for X and Y:

```
>>> v.get_scale_xy()
(0.5, 0.5)
```

If the scale factors are always set to the same value and adjusted equally in tandem, then you can obtain the general scale value as:

>>> v.get\_scale\_max()
0.5

#### **Scaling Limits**

Ginga places a limit on the scale when the scale would result in an aberrant viewing condition. For example, it will cease to increase the scale when the pixel size approaches the window size.

Ginga has a feature for setting arbitrary hard limits on the minimum and maximum scale.

To get the scale limits (returns minimum and maximum scale):

```
>>> v.get_scale_limits()
(1e-05, 10000.0)
```

To set the scale limits:

```
>>> v.set_scale_limits(min_scale, max_scale)
```

The limits apply to all dimensions. A value of None (the default) means that no artificial limit will be imposed.

# 5.2.4 Zooming

Although Ginga uses scale factors to accomplish image scaling, it also supports the concept of zooming via *levels*. It does this by mapping a zoom level to a scale factor according to the *zoom algorithm* (see following section) in use.

Zoom algorithms assume that a 1:1 scale is always zoom level 0. Providing a negative zoom level zooms "out" (smaller scale) while a positive value zooms "in" (larger scale).

Set a zoom level:

Zoom in one level:

```
>>> v.zoom_in()
```

Zoom out three levels:

```
>>> v.zoom_out(3)
```

Zoom so that the loaded image fits the window:

```
>>> v.zoom_fit()
```

Get the current zoom level corresponding to the current scale:

```
>>> v.get_zoom()
-8.544
```

**Note:** Zoom levels need not be integers, and there should be an invertable mapping between scale and zoom level defined by the zoom algorithm.

#### **Zoom Algorithms**

There are two main zoom algorithms, "step" and "rate", for determining zoom levels and corresponding scales. The step algorithm just zooms in integer multiples of the pixels:  $1, 2, 3, 4, \ldots$  or 1/2, 1/3, 1/4, etc. The rate algorithm simply applies a multiplier to the current scale to arrive at the new scale. This can be more appropriate to achieve a faster (or slower) rate of zoom than stepping.

Get the zoom algorithm in use:

```
>>> v.get_zoom_algorithm()
'step'
```

Set the zoom algorithm:

```
>>> v.set_zoom_algorithm('rate')
```

Note: Corresponds to the viewer setting zoom\_algorithm.

#### Get the zoom rate:

```
>>> v.get_zoomrate()
1.4142135623730951
```

#### Set the zoom rate:

```
>>> v.set_zoomrate(1.1)
```

**Note:** Corresponds to the viewer setting zoom\_rate. The zoom rate should be defined as a value greater than 1. This value is ignored when the "step" algorithm is in use.

## 5.2.5 Panning

The "pan position" defines the point on which the viewer should be centered. Normally this is specified in data coordinates, but it can also be specified in world coordinates if a valid WCS is available in an image that is loaded.

Get the pan position in data coordinates (the default):

```
>>> v.get_pan()
(1136.0, 2136.5)
```

Set the pan position:

```
>>> v.set_pan((500.0, 1500.0))
```

Get the pan position in world coordinates (in this case, degrees):

```
>>> v.get_pan(coord='wcs')
(300.16929984148425, 22.80602873666544)
```

Set the pan position in world coordinates:

```
>>> v.set_pan((298.21, 24.6), coord='wcs')
```

**Note:** Corresponds to the viewer settings pan and pan\_coord.

Pan to 25% of the X axis and 75% of the Y axis:

```
>>> v.panset_pct(0.25, 0.75)
```

Center the image (i.e., pan to center):

```
>>> v.center_image()
```

Get the coordinates in the actual data corresponding to the area shown in the display for the current zoom level and pan:

```
>>> v.get_pan_rect()
array([[ 886. , 1886.5],
        [ 886. , 2386.5],
        [1386. , 2386.5],
        [1386. , 1886.5]])
```

The values are returned as corners lower-left, upper-left, upper-right, lower-right.

# 5.2.6 Transforms

The Ginga viewer provides three quick transforms in addition to rotation (described below). These are flipping in the X axis, flipping in the Y axis, and swapping axes. These three transforms can be set in a single call, with three booleans, in the order just listed.

Flip the view in the X dimension:

```
>>> v.transform(True, False, False)
```

Flip the view in the Y dimension:

```
>>> v.transform(False, True, False)
```

Flip the view in the X dimension and swap the X and Y axes:

>>> v.transform(True, False, True)

Get the existing transforms:

```
>>> v.get_transforms()
(True, False, True)
```

**Note:** Corresponds to the viewer settings flip\_x, flip\_y and swap\_xy.

Attempt to orient the viewer according to the image loaded (may set transforms to accomplish this):

```
>>> v.auto_orient()
```

# 5.2.7 Rotation

The Ginga viewer can also rotate the image. Values are specified in degrees.

Rotate the view 45 degrees:

```
>>> v.rotate(45.0)
```

#### Get current rotation:

```
>>> v.get_rotation()
45.0
```

Note: Corresponds to the viewer setting rot\_deg.

## 5.2.8 Cut Levels

The cut levels are Ginga's lexicon for the low and high values used to establish the mapping from data values to the minimum and maximum pixel luminance values in the viewer. Values in the data below the low cut value will be driven to the bottom luminance value and values above the high cut value will be driven to the top luminance value. The values in between are scaled to the range between these values.

Setting cut levels on the viewer:

```
>>> v.cut_levels(lo_val, hi_val)
```

Get current cut levels:

```
>>> v.get_cut_levels()
(440.6118816303353, 606.8032622632695)
```

Note: Corresponds to the viewer setting cuts.

#### Auto cut levels

Calculating and applying an auto cut levels (aka "auto levels"), using the current algorithm setting and parameters:

>>> v.auto\_levels()

Find out what automatic cut levels algorithms are available:

```
>>> v.get_autocut_methods()
('minmax', 'median', 'histogram', 'stddev', 'zscale')
```

Set viewer to use a specific algorithm, with parameters:

```
>>> v.set_autocut_params('histogram', pct=0.90)
```

**Note:** Every auto cuts algorithm is encapsulated into an auto cuts class. The parameters can vary according to the parameters of the algorithm and are passed as keyword parameters to this call.

Retrieve the current autocuts object:

```
>>> v.autocuts
<ginga.AutoCuts.Histogram at 0x7fb404a19dd8>
```

Explicitly set the autocuts object directly:

```
>>> from ginga.AutoCuts import ZScale
>>> ac = ZScale(v.get_logger(), contrast=0.4)
>>> v.set_autocuts(ac)
```

Note: Unless you are using a custom autocuts class it is generally easier to just use the set\_autocut\_params() method.

## 5.2.9 Color Distribution

The color distribution algorithm distributes the values in the image *after* the cut levels to the colors defined by the color map. This normally describes a mapping curve such as linear, logarithmic, etc.

Find out what color distribution algorithms are available:

```
>>> v.get_color_algorithms()
['linear', 'log', 'power', 'sqrt', 'squared', 'asinh', 'sinh', 'histeq']
```

Set a specific color distribution algorithm:

```
>>> v.set_color_algorithm('log')
```

Find out which one is being used:

```
>>> v.get_settings().get('color_algorithm')
'log'
```

## 5.2.10 Color Map

Find out what color maps are available:

```
>>> from ginga import cmap
>>> cmap.get_names()
['Accent',
 'Accent_r',
 'afmhot',
 'afmhot_r',
 '...
'YlOrBr_r',
'YlOrRd',
'YlOrRd_r']
```

Set a color map:

>>> v.set\_color\_map('YlOrBr\_r')

Find out which one is being used:

```
>>> v.get_settings().get('color_map')
'YlOrBr_r'
```

Enable matplotlib color maps to be available (if matplotlib is installed):

>>> cmap.add\_matplotlib\_cmaps()

Invert the color map:

>>> v.invert\_cmap()

Shift the color map by pct percent:

>>> v.shift\_cmap(0.2)

Stretch/shrink and shift color map:

```
>>> v.scale_and_shift_cmap(scale_pct, shift_pct)
```

### 5.2.11 Intensity Map

**Note:** Intensity maps are a feature that largely duplicates the functionality of color distributions (see above). It performs a remapping of the colors after the color mapping phase has been applied. We suggest that most users will want to leave the default setting of 'ramp', which is leaves the color map as is.

Find out what intensity maps are available:

```
>>> from ginga import imap
>>> imap.get_names()
['equa',
  'expo',
  'gamma',
  'jigsaw',
  'lasritt',
  'lasritt',
  'log',
  'neglog',
  'neglog',
  'null',
  'ramp',
  'stairs',
  'ultrasmooth']
```

Set an intensity map:

```
>>> v.set_intensity_map('lasritt')
```

Find out which one is being used:

```
>>> v.get_settings().get('intensity_map')
'lasritt'
```

### 5.2.12 Auto configuration

Ginga has some settings that control whether certain initializations are performed when a new image is set in the viewer.

Enable auto orientation of new image (see auto\_orient() under "Transforms"):

>>> v.enable\_auto\_orient(True)

Note: Corresponds to the viewer setting auto\_orient.

Enable auto centering (pan to center of new image):

>>> v.enable\_autocenter('on')

Note: Corresponds to the viewer setting autocenter.

Enable auto cuts (calculate and set cut levels of new image):

>>> v.enable\_autocuts('on')

Note: Corresponds to the viewer setting autocuts.

Enable auto zoom (scale to fit new image to window):

>>> v.enable\_autozoom('on')

Note: Corresponds to the viewer setting autozoom.

The autocenter, autocuts, and autozoom settings allow the following values:

- 'on': apply to every new image
- 'once': apply to the first image set only, then turn 'off'
- · 'override': apply to each image until the user overrides manually, then turn 'off', and
- 'off': never apply

### 5.2.13 Miscellaneous Operations

Set the background color of the viewer:

>>> v.set\_bg(0.2, 0.2, 0.2)

Note: Corresponds to the viewer setting color\_bg.

Set the foreground color of the viewer (used for some text overlays):

>>> v.set\_fg(0.8, 0.9, 0.7)

Note: Corresponds to the viewer setting color\_fg.

Put a message onscreen for 2 seconds:

>>> v.onscreen\_message("Hello, world!", delay=2.0)

Get the last position of the cursor in data coordinates:

```
>>> v.get_last_data_xy()
(782.4466094067262, 2136.5)
```

Whether the viewer widget should take focus when the cursor enters the window:

>>> v.set\_enter\_focus(**True**)

Note: Corresponds to the viewer setting enter\_focus.

Get the bounding box of viewer extents (returns lower-left and upper-right corners of the bounding box):

```
>>> v.get_limits()
((0.0, 0.0), (2272.0, 4273.0))
```

**Note:** Normally the limits are defined by an image that is loaded, if any. But they can also be overridden, as shown below.

Set explicit limits for the viewer:

>>> v.set\_limits(((250.0, 250.0), (2500.0, 2500.0)))

**Note:** Corresponds to the viewer setting limits.

## 5.3 Ginga Canvas Graphics

This chapter describes the basic architecture of Ginga's canvas-viewer-renderer model, and describes how to do graphics operations on canvases.

## 5.3.1 Canvases and Canvas Objects

Ginga's canvas is based on the DrawingCanvas class. On the canvas can be placed a number of different kinds of *canvas objects*, including many geometric shapes. The set of canvas objects includes:

- Text: a piece of text having a single point coordinate.
- Polygon: a closed polygon defined by N points.
- Path: an open polygon defined by N points.
- Box: a rectangular shape defined by a single center point, two radii and a rotation angle.
- Ellipse: an elliptical shape defined by a single center point, two radii and a rotation angle.
- Triangle: an equilateral triangular shape defined by a single center point, two radii and a rotation angle.
- Circle: a circular shape defined by a center point and a radius.
- Point: a marker for a point defined by a single point and a radius for the "arms".
- Rectangle a rectangular shape defined by two points.
- Line a line defined by two points.
- RightTriangle a right triangle defined by two points.
- Compass a compass defined by a point and a radius.
- Ruler a ruler defined by two points.
- Crosshair a crosshair defined by one point.
- Annulus an annulus defined by one point, a radius and a width.
- Annulus2R an annulus defined by one point, two radii and two widths.
- Image a raster image anchored by a point.
- NormImage a subclass of Image, with rendering done with the aid of a colormap, a color distribution algorithm (linear, log, etc), and defined low and high cut levels.
- CompoundObject: a compound object combining a series of other canvas objects.
- Canvas: a transparent subcanvas on which items can be placed.
- DrawingCanvas: Like a Canvas, but also can support manual drawing operations initiated in a viewer to create shapes on itself.
- ColorBar: a bar with a color range and ticks and value markers to help indicate the mapping of color to the value range of the data.
- ModeIndicator: a small rectangular overlay with text indicating that the user has entered a special keyboard/mouse mode.

All canvas objects are subclasses of CanvasObjectBase and may also contain mixin classes that define common attributes or behavior. For example, Line, Ruler and RightTriangle are all subclasses of the mixin class TwoPointMixin.

**Note:** In most general canvas systems you can layer objects in any order. In Ginga there is an optimization of canvas redrawing that merges image bitmaps before updating other kinds of canvas objects. This means that while images can be stacked in any order, effectively you cannot have other objects appear *underneath* image objects. For most uses of the viewer this is not a big limitation.

### 5.3.2 Viewers

All Ginga viewers are subclasses of ImageViewBase. These objects implement a viewport onto a DrawingCanvas object. Each viewer contains a handle to a canvas and provides a particular view onto that canvas defined by:

- dimensions of their viewport (i.e. the height and width of the native widget's window into which the viewer is rendering),
- scale in X and Y dimensions,
- a pan position linking the center of the viewport to a canvas coordinate,
- a transform consisting of possible flips in X, Y axes and/or swapping of X/Y axes, and
- a rotation.

Two different ImageView-based viewers can share the same canvas handle, providing different views into the same canvas. Another typical arrangement for sharing is where each viewer has a private canvas, and on each private canvas is placed a shared transparent subcanvas, an arrangement which allows each viewer to have a mix of private and shared canvas objects. Another common idiom is to layer multiple DrawingCanvas objects to more easily manage multiple collections of overlaid graphics.

The various subclasses of ImageView are designed to render into a different widget set's "native" canvas using a CanvasRenderer customized for that target.

### 5.3.3 Support for Astropy regions

Ginga module plotting shapes То provides а for Astropy regions on canvases. use this, import ginga.util.ap\_regions module of the three the and one use module functions astropy\_region\_to\_ginga\_canvas\_object, add region, or ginga\_canvas\_object\_to\_astropy\_region.

astropy\_region\_to\_ginga\_canvas\_object takes a regions shape and returns a Ginga canvas object that most closely implements the shape. The object returned can be used like any Ginga canvas object: it can be used in a compound object, added to a canvas, etc. Assuming you have a viewer v and an Astropy region r:

```
from ginga.util import ap_region
obj = ap_region.astropy_region_to_ginga_canvas_object(r)
canvas = v.get_canvas()
canvas.add(obj)
```

add\_region is a convenience method for both converting an object and adding it to a canvas.

ap\_region.add\_region(canvas, r)

ginga\_canvas\_object\_to\_astropy\_region provides the reverse transformation, taking a Ginga canvas object and converting it to the closest representation as an Astropy region.

r = ap\_region.ginga\_canvas\_object\_to\_astropy\_region(obj)

# 5.4 Developing with Ginga

• modindex

Developers interested in using Ginga in their project will probably follow one of two logical development paths:

- using Ginga toolkit classes in a program of their own design, or
- starting with the full-featured reference viewer that comes with Ginga and customizing it for some special purpose, typically by modifying one of the plugins or writing a new plugin.

The first approach is probably best for when the developer has a custom application in mind, needs a minimal but powerful viewer or wants to develop an entirely new full-featured viewer. Developers interested in this direction should head over to the chapter on the viewer object (see *Using the Basic Ginga Viewer Object in Python Programs*).

The second approach is probably best for end users or developers that are mostly satisfied with the reference viewer as a general purpose tool and want to add some specific enhancements or functionality. Because the reference viewer is based on a flexible plugin architecture this is fairly straightforward to do.


# 5.4.1 Writing plugins for the reference viewer


The philosophy behind the design of the reference viewer distributed with the Ginga is that it is simply a flexible layout shell for instantiating instances of the Ginga view widgets described in the earlier section. All of the other important pieces of a modern FITS viewer–a panning widget, information panels, zoom widget, analysis panes–are implemented as plugins: encapsulated modules that interface with the viewing shell using a standardized API. This makes it easy to customize and to add, change or remove functionality in a very modular, flexible way.

The Ginga viewer divides the application window GUI into containers that hold either viewing widgets or plugins. The view widgets are called "channels" in the viewer nomenclature, and are a means of organizing images in the viewer, functioning much like "frames" in other viewers. A channel has a name and maintains its own history of images that have cycled through it. The user can create new channels as needed. For example, they might use different channels for different kinds of images: camera vs. spectrograph, or channels organized by CCD, or by target, or raw data vs. quick look, etc. In the default layout, the channel tabs are in the large middle pane, while the plugins occupy the left and right panes. Other layouts are possible, by simply changing a table used in the startup script.

Ginga distinguishes between two types of plugin: *global* and *local*. Global plugins are used where the functionality is generally enabled during the entire session with the viewer and where the plugin is active no matter which channel is currently under interaction with the user. Examples of global plugins include a panning view (a small, bird's-eye view of the image that shows a panning rectangle and allows graphical positioning of the pan region), a zoomed view (that shows an enlarged cutout of the area currently under the cursor), informational displays about world coordinates, FITS headers, thumbnails, etc. Figure *Two global plugins: Pan (top) and Info (bottom), shown sharing a tab.* shows an example of two global plugins occupying a notebook tab.

Local plugins are used for modal operations with images in specific channels. For example, the Pick plugin is used to perform stellar evaluation of objects, finding the center of the object and giving informational readings of the exact celestial coordinates, image quality, etc. The Pick plugin is only visible while the user has it open, and does not capture the mouse actions unless the channel it is operating on is selected. Thus one can have two different Pick operations going on concurrently on two different channels, for example, or a Pick operation in a camera channel, and a Cuts (line cuts) operation on a spectrograph channel. Figure *The Pick local plugin, shown occupying a tab.* shows an example of the Pick local plugin occupying a notebook tab.





### Anatomy of a Local Ginga Plugin

Let's take a look at a local plugin to understand the API for interfacing to the Ginga shell. In Listing 2, we show a stub for a local plugin.

```
from ginga import GingaPlugin
class MyPlugin (GingaPlugin.LocalPlugin):
    def __init__(self, fv, fitsimage):
        super(MyPlugin, self).__init__(fv, fitsimage)
    def build_gui(self, container):
        pass
    def start(self):
        pass
    def stop(self):
        pass
    def pause(self):
        pass
    def resume(self):
        pass
    def redo(self):
        pass
    def str (self):
        return 'myplugin'
```

#### A little more fleshed out example: MyLocalPlugin

This is a skeleton for a local plugin. It is also good example of something that actually runs and can be copied as a template for a local plugin. This plugin is distributed with the Ginga package and can be loaded and invoked from a terminal:

ginga --plugins=MyLocalPlugin --loglevel=20 --log=/tmp/ginga.log

The plugin will be accessible via the "Operation" button in the Plugin Manager bar.

```
from ginga import GingaPlugin
from ginga.misc import Widgets
# import any other modules you want here--it's a python world!
class MyLocalPlugin(GingaPlugin.LocalPlugin):
    def __init__(self, fv, fitsimage):
        """
        This method is called when the plugin is loaded for the first
        time. ``fv`` is a reference to the Ginga (reference viewer) shell
        and ``fitsimage`` is a reference to the specific viewer
        object associated with the channel on which the plugin is being
```

```
invoked.
    You need to call the superclass initializer and then do any local
    initialization.
    .....
    super(MyLocalPlugin, self).__init__(fv, fitsimage)
    # your local state and initialization code goes here
def build_gui(self, container):
    .....
    This method is called when the plugin is invoked. It builds the
    GUI used by the plugin into the widget layout passed as
    ``container``.
    This method may be called many times as the plugin is opened and
    closed for modal operations. The method may be omitted if there
    is no GUI for the plugin.
    This specific example uses the GUI widget set agnostic wrappers
    to build the GUI, but you can also just as easily use explicit
    toolkit calls here if you only want to support one widget set.
    .....
    top = Widgets.VBox()
    top.set_border_width(4)
    # this is a little trick for making plugins that work either in
    # a vertical or horizontal orientation. It returns a box container,
    # a scroll widget and an orientation ('vertical', 'horizontal')
    vbox, sw, orientation = Widgets.get_oriented_box(container)
    vbox.set_border_width(4)
    vbox.set_spacing(2)
    # Take a text widget to show some instructions
    self.msgFont = self.fv.getFont("sansFont", 12)
    tw = Widgets.TextArea(wrap=True, editable=False)
    tw.set_font(self.msgFont)
    self.tw = tw
    # Frame for instructions and add the text widget with another
    # blank widget to stretch as needed to fill emp
    fr = Widgets.Frame("Instructions")
    vbox2 = Widgets.VBox()
    vbox2.add_widget(tw)
    vbox2.add_widget(Widgets.Label(''), stretch=1)
    fr.set_widget(vbox2)
    vbox.add_widget(fr, stretch=0)
    # Add a spacer to stretch the rest of the way to the end of the
    # plugin space
    spacer = Widgets.Label('')
    vbox.add_widget(spacer, stretch=1)
    # scroll bars will allow lots of content to be accessed
    top.add_widget(sw, stretch=1)
    # A button box that is always visible at the bottom
    btns = Widgets.HBox()
    btns.set_spacing(3)
```

```
(continued from previous page)
```

```
# Add a close button for the convenience of the user
    btn = Widgets.Button("Close")
    btn.add_callback('activated', lambda w: self.close())
    btns.add_widget(btn, stretch=0)
    btns.add_widget(Widgets.Label(''), stretch=1)
    top.add_widget(btns, stretch=0)
    # Add our GUI to the container
    container.add_widget(top, stretch=1)
    # NOTE: if you are building a GUI using a specific widget toolkit
    # (e.g. Qt) GUI calls, you need to extract the widget or layout
    # from the non-toolkit specific container wrapper and call on that
    # to pack your widget, e.g.:
    #cw = container.get widget()
    #cw.addWidget(widget, stretch=1)
def close(self):
    .....
    Example close method. You can use this method and attach it as a
    callback to a button that you place in your GUI to close the plugin
    as a convenience to the user.
    .....
    chname = self.fv.get_channel_name(self.fitsimage)
    self.fv.stop_local_plugin(chname, str(self))
    return True
def start(self):
    .....
    This method is called just after ``build_gui()`` when the plugin
    is invoked. This method may be called many times as the plugin is
    opened and closed for modal operations. This method may be omitted
    in many cases.
    .....
    self.tw.set_text("""This plugin doesn't do anything interesting.""")
    self.resume()
def pause(self):
    This method is called when the plugin loses focus.
    It should take any actions necessary to stop handling user
    interaction events that were initiated in ``start()`` or
    ``resume()``.
    This method may be called many times as the plugin is focused
    or defocused. It may be omitted if there is no user event handling
    to disable.
    .....
   pass
def resume(self):
    .....
    This method is called when the plugin gets focus.
    It should take any actions necessary to start handling user
    interaction events for the operations that it does.
    This method may be called many times as the pluqin is focused or
    defocused. The method may be omitted if there is no user event
    handling to enable.
```

```
.....
    pass
def stop(self):
    .....
    This method is called when the plugin is stopped.
    It should perform any special clean up necessary to terminate
    the operation. The GUI will be destroyed by the plugin manager
    so there is no need for the stop method to do that.
    This method may be called many times as the plugin is opened and
    closed for modal operations, and may be omitted if there is no
    special cleanup required when stopping.
    .....
    pass
def redo(self):
    .....
    This method is called when the plugin is active and a new
    image is loaded into the associated channel. It can optionally
    redo the current operation on the new image. This method may be
    called many times as new images are loaded while the plugin is
    active. This method may be omitted.
    .....
    pass
def __str__(self):
    .....
    This method should be provided and should return the lower case
    name of the plugin.
    .....
    return 'mylocalplugin'
```

The instance variables "fv" and "fitsimage" will be assigned by the superclass initializer to self.fv and self.fitsimage–these are the reference viewer "shell" and the ginga display object respectively. To interact with the viewer you will be calling methods on one or both of these objects.

The "fitsimage" object is the ginga image viewer object associated with the channel. You can get a good idea of how to programmatically manipulate this viewer here *Ginga Image Viewer Operations* and by browsing the source of the many plugins distributed with Ginga. Most of them are not very long or complex. Also, a plugin can include any Python packages or modules that it wants and programming one is essentially similar to writing any other Python program. We suggest picking a plugin that looks or does something similar to what you are interested in, copying it, and modifying it to fit your needs.

#### Launching and Debugging Your Plugin

The easiest way to start out is to create a plugins directory under your ginga configuration area. In a terminal:

mkdir \$HOME/.ginga/plugins

Put your plugin in there (a good one to start with is to modify the MyLocalPlugin example that comes with Ginga):

```
cd .../ginga/examples/reference-viewer
cp MyLocalPlugin.py $HOME/.ginga/plugins/MyPlugin.py
```

To load it when the reference viewer starts (and add some logging to stderr as well as to a file):

ginga --plugins=MyPlugin --loglevel=20 --stderr --log=/tmp/ginga.log

To start the plugin from within the reference viewer, use the Plugin Manager bar just below the color and readout bars. Use the "Operation" menu to select your plugin and it should be launched in the right panel.

If you don't see the name of your plugin in the Operation menu, then there was probably an error trying to load it. Examine the log and search for the name of your plugin–you should find some error message associated with it.

If you select your plugin from the menu, but it doesn't launch a GUI, there may be a problem or error in the plugin file. Again, examine the log and search for the name of your plugin–you should find some error message associated with it. It may help for you to add some debugging messages to your plugin (either using self.logger.debug("...") or simple print statements to stdout) to gauge the progress of building the gui and plugin starting.

If the plugin launches, but encounters an error building the GUI, it should show some error messages (and probably a stack trace) in placeholders in the right panel in the container where it tried to build the GUI or possibly under the Errors tab.

**Note:** Ginga has a feature for quickly reloading plugins to facilitate rapid debugging cycles. If it is not already running, start the "Command Line" plugin from the "Plugins->Debug" menu in the menu bar. If your plugin launched (but has some error), make sure you have closed your plugin by right clicking (or Control + click on Mac touchpad) on the small box representing your plugin in the Plugin Manager bar and selecting "Stop". In the Command Line plugin, there is a small box labeled "Type command here:". Use the command "reload\_local <plugin\_name>"-this will reload the python module representing your plugin and you should be able to immediately restart it using the Plugin Manager bar as described above (if the plugin is of the global plugin variety, use the command "reload\_global" instead).

If you have edited third party modules that are included in the plugin, this will not be enough to pick up those changes.

#### A more complex example: The Ruler Plugin

#

Finally, in Listing 3 we show a completed plugin for Ruler. The purpose of this plugin to draw triangulation (distance measurement) rulers on the image. For reference, you may want to refer to the ruler shown in *The Ruler local plugin GUI*, shown occupying a tab.

```
# Ruler.py -- Ruler plugin for Ginga reference viewer
#
from ginga import GingaPlugin
from ginga.gw import Widgets
class Ruler(GingaPlugin.LocalPlugin):
    def __init__(self, fv, fitsimage):
        # superclass defines some variables for us, like logger
        super(Ruler, self).__init__(fv, fitsimage)
        self.rulecolor = 'green'
        self.layertag = 'ruler-canvas'
        self.ruletag = None
        self.dc = fv.get_draw_classes()
        canvas = self.dc.DrawingCanvas()
        canvas.enable_draw(True)
        canvas.enable_dit(True)
        canvas.set_drawtype('ruler', color='cyan')
```




Fig. 3: The Ruler local plugin GUI, shown occupying a tab.

```
(continued from previous page)
```

```
canvas.set_callback('draw-event', self.wcsruler)
    canvas.set_callback('draw-down', self.clear)
    canvas.set_callback('edit-event', self.edit_cb)
    canvas.set_draw_mode('draw')
    canvas.set_surface(self.fitsimage)
    canvas.register_for_cursor_drawing(self.fitsimage)
    canvas.name = 'Ruler-canvas'
    self.canvas = canvas
    self.w = None
    self.unittypes = ('arcmin', 'degrees', 'pixels')
    self.units = 'arcmin'
def build_gui(self, container):
   top = Widgets.VBox()
    top.set_border_width(4)
    vbox, sw, orientation = Widgets.get_oriented_box(container)
    vbox.set_border_width(4)
    vbox.set_spacing(2)
   self.msgFont = self.fv.get_font("sansFont", 12)
   tw = Widgets.TextArea(wrap=True, editable=False)
    tw.set_font(self.msgFont)
    self.tw = tw
    fr = Widgets.Expander("Instructions")
    fr.set_widget(tw)
   vbox.add_widget(fr, stretch=0)
    fr = Widgets.Frame("Ruler")
    captions = (('Units:', 'label', 'Units', 'combobox'),
    w, b = Widgets.build_info(captions, orientation=orientation)
    self.w = b
    combobox = b.units
    for name in self.unittypes:
       combobox.append_text(name)
    index = self.unittypes.index(self.units)
    combobox.set_index(index)
    combobox.add_callback('activated', lambda w, idx: self.set_units())
    fr.set_widget(w)
    vbox.add_widget(fr, stretch=0)
   mode = self.canvas.get_draw_mode()
   hbox = Widgets.HBox()
   btn1 = Widgets.RadioButton("Draw")
   btn1.set_state(mode == 'draw')
   btn1.add_callback('activated', lambda w, val: self.set_mode_cb('draw', val))
   btn1.set_tooltip("Choose this to draw a ruler")
    self.w.btn draw = btn1
   hbox.add_widget(btn1)
    btn2 = Widgets.RadioButton("Edit", group=btn1)
```

```
btn2.set_state(mode == 'edit')
        btn2.add_callback('activated', lambda w, val: self.set_mode_cb('edit', val))
        btn2.set_tooltip("Choose this to edit a ruler")
        self.w.btn_edit = btn2
        hbox.add_widget(btn2)
        hbox.add_widget(Widgets.Label(''), stretch=1)
        vbox.add_widget(hbox, stretch=0)
        spacer = Widgets.Label('')
        vbox.add_widget(spacer, stretch=1)
        top.add_widget(sw, stretch=1)
       btns = Widgets.HBox()
       btns.set_spacing(3)
        btn = Widgets.Button("Close")
        btn.add_callback('activated', lambda w: self.close())
        btns.add_widget(btn, stretch=0)
        btns.add_widget(Widgets.Label(''), stretch=1)
        top.add_widget(btns, stretch=0)
        container.add_widget(top, stretch=1)
   def set_units(self):
       index = self.w.units.get_index()
       units = self.unittypes[index]
        self.canvas.set_drawtype('ruler', color='cyan', units=units)
        if self.ruletag is not None:
            obj = self.canvas.get_object_by_tag(self.ruletag)
            if obj.kind == 'ruler':
                obj.units = units
                self.canvas.redraw(whence=3)
        return True
   def close(self):
        chname = self.fv.get_channel_name(self.fitsimage)
        self.fv.stop_local_plugin(chname, str(self))
        return True
   def instructions(self):
        self.tw.set_text("""Draw (or redraw) a line with the cursor.
Display the Zoom tab at the same time to precisely see detail while drawing.""")
    def start(self):
       self.instructions()
        # start ruler drawing operation
       p_canvas = self.fitsimage.get_canvas()
        if not p_canvas.has_object(self.canvas):
           p_canvas.add(self.canvas, tag=self.layertag)
        self.canvas.delete_all_objects()
        self.resume()
```

```
(continued from previous page)
```

```
def pause(self):
    self.canvas.ui_set_active(False)
def resume(self):
    self.canvas.ui_set_active(True)
    self.fv.show_status("Draw a ruler with the right mouse button")
def stop(self):
    # remove the canvas from the image
    p_canvas = self.fitsimage.get_canvas()
    try:
        p_canvas.delete_object_by_tag(self.layertag)
    except:
        pass
    self.canvas.ui_set_active(False)
    self.fv.show_status("")
def redo(self):
    obj = self.canvas.get_object_by_tag(self.ruletag)
    if obj.kind != 'ruler':
        return True
    # redraw updates ruler measurements
    self.canvas.redraw(whence=3)
def clear(self, canvas, button, data_x, data_y):
    self.canvas.delete_all_objects()
    self.ruletag = None
    return False
def wcsruler(self, surface, tag):
    obj = self.canvas.get_object_by_tag(tag)
    if obj.kind != 'ruler':
        return True
    # remove the old ruler
    try:
        self.canvas.delete_object_by_tag(self.ruletag)
    except:
        pass
    # change some characteristics of the drawn image and
    # save as the new ruler
    self.ruletag = tag
    obj.color = self.rulecolor
    obj.cap = 'ball'
    self.canvas.redraw(whence=3)
def edit_cb(self, canvas, obj):
    self.redo()
    return True
def edit_select_ruler(self):
    if self.ruletag is not None:
        obj = self.canvas.get_object_by_tag(self.ruletag)
        self.canvas.edit_select(obj)
    else:
        self.canvas.clear_selected()
    self.canvas.update_canvas()
```

```
def set_mode_cb(self, mode, tf):
    if tf:
        self.canvas.set_draw_mode(mode)
        if mode == 'edit':
            self.edit_select_ruler()
        return True

def __str__(self):
        return 'ruler'
#END
```

This plugin shows a standard design pattern typical to local plugins. Often one is wanting to draw or plot something on top of the image below. The CanvasView widget used by Ginga allows this to be done very cleanly and conveniently by adding a DrawingCanvas object to the image and drawing on that. Canvases can be layered on top of each other in a manner analogous to "layers" in an image editing program. Since each local plugin maintains it's own canvas, it is very easy to encapsulate the logic for drawing on and dealing with the objects associated with that plugin. We use this technique in the Ruler plugin. When the plugin is loaded (refer to \_\_init\_\_() method), it creates a canvas, enables drawing on it, sets the draw type and registers a callback for drawing events. When start() is called it adds that canvas to the widget. When stop() is called it removes the canvas from the widget (but does not destroy the canvas). pause() disables user interaction on the canvas and resume() reenables that interaction. redo() simply redraws the ruler with new measurements taken from any new image that may have been loaded. In the \_\_init\_\_() method you will notice a set\_surface() call that associates this canvas with a ImageView-based widget—this is the key for the canvas to utilize WCS information for correct plotting. All the other methods shown are support methods for doing the ruler drawing operation and interacting with the plugin GUI.

### Writing a Global Plugin

The last example was focused on writing a local plugin. Global plugins employ a nearly identical API to that shown in Listing 2, except that the constructor does not take a fitsimage parameter. pause () and resume () can safely be omitted. Like local plugins, build\_gui() can be omitted if there is no GUI associated with the plugin.

### A template: MyGlobalPlugin

This is a skeleton for a global plugin, and serves as a decent example of something that can be copied as a template for a global plugin. This plugin is distributed with the Ginga package and can be loaded and invoked from a terminal:

ginga --modules=MyGlobalPlugin --loglevel=20 --log=/tmp/ginga.log

The plugin will be started at program startup and can be seen in the "MyGlobalPlugin" tab in the right panel. Watch the status message as you create new channels, delete channels or load images into channels.

```
from ginga import GingaPlugin
from ginga.misc import Widgets
# import any other modules you want here--it's a python world!
class MyGlobalPlugin(GingaPlugin.GlobalPlugin):
    def __init__(self, fv):
        """
        This method is called when the plugin is loaded for the first
```

```
``fv`` is a reference to the Ginga (reference viewer) shell.
    time.
    You need to call the superclass initializer and then do any local
    initialization.
    .....
    super(MyGlobalPlugin, self).___init___(fv)
    # Your initialization here
    # Create some variables to keep track of what is happening
    # with which channel
   self.active = None
    # Subscribe to some interesting callbacks that will inform us
    # of channel events. You may not need these depending on what
    # your plugin does
   fv.set_callback('add-channel', self.add_channel)
   fv.set_callback('delete-channel', self.delete_channel)
   fv.set_callback('active-image', self.focus_cb)
def build_gui(self, container):
    .....
    This method is called when the plugin is invoked. It builds the
   GUI used by the plugin into the widget layout passed as
    ``container``.
   This method could be called several times if the plugin is opened
   and closed. The method may be omitted if there is no GUI for the
   plugin.
   This specific example uses the GUI widget set agnostic wrappers
   to build the GUI, but you can also just as easily use explicit
   toolkit calls here if you only want to support one widget set.
    .....
   top = Widgets.VBox()
   top.set_border_width(4)
    # this is a little trick for making plugins that work either in
    # a vertical or horizontal orientation. It returns a box container,
    # a scroll widget and an orientation ('vertical', 'horizontal')
   vbox, sw, orientation = Widgets.get_oriented_box(container)
   vbox.set border width(4)
   vbox.set_spacing(2)
    # Take a text widget to show some instructions
   self.msgFont = self.fv.getFont("sansFont", 12)
   tw = Widgets.TextArea(wrap=True, editable=False)
   tw.set_font(self.msqFont)
   self.tw = tw
    # Frame for instructions and add the text widget with another
    # blank widget to stretch as needed to fill emp
   fr = Widgets.Frame("Status")
   vbox2 = Widgets.VBox()
   vbox2.add widget(tw)
   vbox2.add_widget(Widgets.Label(''), stretch=1)
   fr.set_widget(vbox2)
   vbox.add_widget(fr, stretch=0)
```

```
# Add a spacer to stretch the rest of the way to the end of the
    # plugin space
    spacer = Widgets.Label('')
    vbox.add_widget(spacer, stretch=1)
    # scroll bars will allow lots of content to be accessed
    top.add_widget(sw, stretch=1)
    # A button box that is always visible at the bottom
    btns = Widgets.HBox()
    btns.set_spacing(3)
    # Add a close button for the convenience of the user
    btn = Widgets.Button("Close")
    btn.add_callback('activated', lambda w: self.close())
    btns.add_widget(btn, stretch=0)
    btns.add_widget(Widgets.Label(''), stretch=1)
    top.add_widget(btns, stretch=0)
    # Add our GUI to the container
    container.add_widget(top, stretch=1)
    # NOTE: if you are building a GUI using a specific widget toolkit
    # (e.g. Qt) GUI calls, you need to extract the widget or layout
    # from the non-toolkit specific container wrapper and call on that
    # to pack your widget, e.g.:
    #cw = container.get_widget()
    #cw.addWidget(widget, stretch=1)
def get_channel_info(self, fitsimage):
    chname = self.fv.get_channelName(fitsimage)
    chinfo = self.fv.get_channelInfo(chname)
    return chinfo
def set_info(self, text):
    self.tw.set_text(text)
# CALLBACKS
def add_channel(self, viewer, chinfo):
    .....
    Callback from the reference viewer shell when a channel is added.
    .....
    self.set_info("Channel '%s' has been added" % (
            chinfo.name))
    # Register for new image callbacks on this channel's canvas
    fitsimage = chinfo.fitsimage
    fitsimage.set_callback('image-set', self.new_image_cb)
def delete_channel(self, viewer, chinfo):
    .....
    Callback from the reference viewer shell when a channel is deleted.
    .....
    self.set info("Channel '%s' has been deleted" % (
            chinfo.name))
    return True
```

```
def focus_cb(self, viewer, fitsimage):
    .....
    Callback from the reference viewer shell when the focus changes
    between channels.
    .....
    chinfo = self.get_channel_info(fitsimage)
    chname = chinfo.name
    if self.active != chname:
        # focus has shifted to a different channel than our idea
        # of the active one
        self.active = chname
        self.set_info("Focus is now in channel '%s'" % (
            self.active))
    return True
def new_image_cb(self, fitsimage, image):
    .....
    Callback from the reference viewer shell when a new image has
    been added to a channel.
    .....
    chinfo = self.get_channel_info(fitsimage)
    chname = chinfo.name
    # Only update our GUI if the activity is in the focused
    # channel
    if self.active == chname:
        imname = image.get('name', 'NONAME')
        self.set_info("A new image 'ss' has been added to channel ss" s (
            imname, chname))
    return True
def start(self):
    .....
    This method is called just after ``build_gui()`` when the plugin
    is invoked. This method could be called more than once if the
    plugin is opened and closed. This method may be omitted
    in many cases.
    .....
   pass
def stop(self):
    .....
    This method is called when the plugin is stopped.
    It should perform any special clean up necessary to terminate
    the operation. This method could be called more than once if
    the plugin is opened and closed, and may be omitted if there is no
    special cleanup required when stopping.
    .....
    pass
def close(self):
    self.fv.stop_global_plugin(str(self))
    return True
def __str__(self):
    .....
```

```
This method should be provided and should return the lower case name of the plugin.
```

```
return 'myglobalplugin'
```

### Writing Separately Installable Plugins

If you want to distribute your plugin(s) as a separately installable package and have Ginga discover them when it starts up, you can use the Ginga Plugin Template to write your own package that installs plugins.

You can include as many plugins in your package as you want. You write your plugins in exactly the same way as described above, and they can be either global or local. For details, clone the repo at the link above and follow the directions in the README.

# 5.5 Using the Basic Ginga Viewer Object in Python Programs

#### • modindex

*The* core design principle of the Ginga project is to make it possible to easily build powerful image viewers in Python with many possible GUI toolkits.

This chapter is for developers who want to use only the Ginga rendering class in a program of their own design (not customizing the reference viewer).

### 5.5.1 Using the basic rendering class in new programs

Ginga basically follows the Model-View-Controller (MVC) design pattern, that is described in more detail in the chapter on internals (see *Ginga Internals*). The "view" classes are rooted in the base class ImageView. Ginga supports backends for different widget sets through various subclasses of this class.

Typically, a developer picks a GUI toolkit that has a supported backend (Gtk 3, Qt 4/5, Tk, matplotlib, HTML5 canvas) and writes a GUI program using that widget set with the typical Python toolkit bindings and API. Where they want a image view pane they instantiate the appropriate subclass of ImageView (usually a CanvasView), and using the get\_widget() call extract the native widget and insert it into the GUI layout. A reference should also be kept to the view object, as this is typically what you will be calling methods on to control the viewer (see *Ginga Image Viewer Operations*).

Ginga does not create any additional GUI components beyond the image pane itself, however it does provide a standard set of keyboard and mouse bindings on the host widget that can be enabled, disabled or changed. The user interface bindings are configurable via a pluggable Bindings class which constitutes the "controller" part of the MVC design. There are a plethora of callbacks that can be registered, allowing the user to create their own custom user interface for manipulating the view. Of course, the developer can add many different GUI widgets from the selected toolkit to supplement or replace these built in controls.

Listing 1 shows a code listing for a simple graphical FITS viewer built using the subclass CanvasView from the module ImageViewQt (screenshot in Figure A simple, "bare bones" FITS viewer written in Qt.) written in around 100 or so lines of Python. It creates a window containing an image view and two buttons. This example will open FITS files dragged and dropped on the image window or via a dialog popped up when clicking the "Open File" button.

```
#! /usr/bin/env python
#
#
# example1_qt.py -- Simple FITS viewer using the Ginga toolkit
```




Fig. 4: A simple, "bare bones" FITS viewer written in Qt.

```
#
                        and Qt widgets.
#
import sys
from ginga.misc import log
from ginga.qtw.QtHelp import QtGui, QtCore
from ginga.qtw.ImageViewQt import CanvasView, ScrolledView
from ginga.util.loader import load_data
class FitsViewer(QtGui.QMainWindow):
    def __init__(self, logger):
        super(FitsViewer, self).___init___()
        self.logger = logger
        # create the ginga viewer and configure it
        fi = CanvasView(self.logger, render='widget')
        fi.enable_autocuts('on')
        fi.set_autocut_params('zscale')
        fi.enable_autozoom('on')
        fi.set_callback('drag-drop', self.drop_file)
        fi.set_bg(0.2, 0.2, 0.2)
        fi.ui_set_active(True)
        self.fitsimage = fi
        # enable some user interaction
        bd = fi.get bindings()
        bd.enable_all(True)
        w = fi.get_widget()
        w.resize(512, 512)
        # add scrollbar interface around this viewer
        si = ScrolledView(fi)
        vbox = QtGui.QVBoxLayout()
        vbox.setContentsMargins(QtCore.QMargins(2, 2, 2, 2))
        vbox.setSpacing(1)
        vbox.addWidget(si, stretch=1)
        hbox = QtGui.QHBoxLayout()
        hbox.setContentsMargins(QtCore.QMargins(4, 2, 4, 2))
        wopen = QtGui.QPushButton("Open File")
        wopen.clicked.connect(self.open_file)
        wquit = QtGui.QPushButton("Quit")
        wquit.clicked.connect(self.quit)
        hbox.addStretch(1)
        for w in (wopen, wquit):
            hbox.addWidget(w, stretch=0)
        hw = QtGui.QWidget()
        hw.setLayout(hbox)
        vbox.addWidget(hw, stretch=0)
```

```
(continued from previous page)
```

```
vw = QtGui.QWidget()
        self.setCentralWidget(vw)
        vw.setLayout(vbox)
    def load_file(self, filepath):
        image = load_data(filepath, logger=self.logger)
        self.fitsimage.set_image(image)
        self.setWindowTitle(filepath)
    def open_file(self):
        res = QtGui.QFileDialog.getOpenFileName(self, "Open FITS file",
                                                 ".", "FITS files (*.fits)")
        if isinstance(res, tuple):
            fileName = res[0]
        else:
            fileName = str(res)
        if len(fileName) != 0:
            self.load_file(fileName)
    def drop_file(self, fitsimage, paths):
        fileName = paths[0]
        self.load_file(fileName)
    def quit(self, *args):
        self.logger.info("Attempting to shut down the application...")
        self.deleteLater()
def main(options, args):
    app = QtGui.QApplication(sys.argv)
    # ginga needs a logger.
    # If you don't want to log anything you can create a null logger by
    # using null=True in this call instead of log_stderr=True
   logger = log.get_logger("example1", log_stderr=True, level=40)
   w = FitsViewer(logger)
   w.resize(524, 540)
   w.show()
   app.setActiveWindow(w)
   w.raise_()
   w.activateWindow()
   if len(args) > 0:
        w.load_file(args[0])
    app.exec_()
if __name__ == '__main__':
   main(None, sys.argv[1:])
```

Looking at the constructor for this particular viewer, you can see where we create a CanvasView object. On this object we enable automatic cut levels (using the 'zscale' algorithm), configure it to auto zoom the image to fit the window and set a callback function for files dropped on the window. We extract the user-interface bindings with get\_bindings(), and on this object enable standard user interactive controls for all the possible key and mouse

operations. We then extract the platform-specific widget (Qt-based, in this case) using get\_widget() and pack it into a Qt container along with a couple of buttons to complete the viewer.

Scanning down the code a bit, we can see that whether by dragging and dropping or via the click to open, we ultimately call the load\_file() method to get the data into the viewer. load\_file() creates an AstroImage object (the "model" part of our MVC design), which is then passed to the viewer via the set\_image() method. AstroImage objects have methods for ingesting data via a file path, an astropy.io.fits HDU or a bare Numpy data array. For a reference on the model, see here:ref:\_ch-image-data-wrappers.

Many of these sorts of examples for all supported backends are contained in the examples directory in the source distribution.

For a list of many methods provided by the viewer object see this reference *Ginga Image Viewer Operations*. You can also click on the module index link at the top of this chapter and then click on the link for ImageViewBase.

### **Graphics plotting with Ginga**

A CanvasView actually pairs a view with a canvas object (in particular a DrawingCanvas object). You can get more detail about canvases and the objects they support (see *Ginga Canvas Graphics*). A variety of graphical shapes are available, and plotted objects scale, transform and rotate seamlessly with the viewer.

### **Rendering into Matplotlib Figures**

Ginga can also render directly into a Matplotlib Figure, which opens up possibilities for overplotting beyond the limited capabilities of the Ginga canvas items. See the examples under "examples/matplotlib" for ideas, particularly "example4\_mpl.py".

### Rendering into HTML5 canvases

Ginga can render onto HTML5 canvases displayed in a web browser. This opens up interesting possibilities for serverbased remote viewing tools. See the examples under "examples/pg", particularly "example2\_pg.py".

### Writing widget toolkit independent code

You can write code that allows the widget set to be abstracted by Ginga's widget wrappers. This is the same technique used to allow the reference viewer to switch between supported toolkits using the "-t" command line option. Currently only Qt (4/5), Gtk (3), and HTML5 (to a more limited degree) are supported, and there are some limitations compared to developing using a native toolkit directly. Nevertheless, the ability to target different platforms just by changing a command line option is a very interesting proposition.

See the examples under "examples/gw", particularly "example2.py".

# 5.6 Using Ginga with Jupyter

Ginga has the following modules available to support visualization in Jupyter Notebook or Lab:

- ginga.web.jupyterw uses ipywidgets; while
- ginga.web.pgw uses HTML5.

Example ipynb files are provided to illustrate basic usage of these modules.




Fig. 5: An example of a CanvasView widget with graphical overlay.

# 5.7 Ginga Internals

This chapter explains the secret inner workings of Ginga and its classes so that you can subclass them and use them in your own applications.

## 5.7.1 Introduction

Ginga uses a version of the Model-View-Controller design pattern. The MVC pattern spells out a division of responsibilities and encapsulation where the Model provides various ways to access and interface to the data, the View provides ways to display the data and the Controller provides the methods and user interface hooks for controlling the view.

### The Model




Fig. 6: Hierarchy of Ginga AstroImage class

The Model classes are rooted in the base class BaseImage. The basic interface to the data is expected to be a Numpylike array object that is obtained via the get\_data() method on the model. It also provides methods for obtaining scaled, cutouts and transformed views of the data, and methods for getting and setting key-value like metadata.

There are two subclasses defined on BaseImage: RGBImage and AstroImage. RGBImage is used for displaying 3 channel RGB type images such as JPEG, TIFF, PNG, etc. AstroImage is the subclass used to represent astronomical images and its organization is shown in Figure *Hierarchy of Ginga AstroImage class*. It has two delegate objects devoted to handling World Coordinate System transformations and file IO. There is also a mixin class, LayerImage that can be used to create layered images with alpha compositing on each layer.

New models can be created, subclassing from BaseImage or AstroImage. As long as the model duck types like a BaseImage it can be loaded into a view object with the set\_image() method. AstroImage provides convenience methods for accessing WCS information that may be necessary when using the model in canvas subclasses of a View that allow graphics drawing.

The View




Fig. 7: Class structure of Ginga basic widget viewer

Figure *Class structure of Ginga basic widget viewer* shows the class inheritance of the ImageViewZoom class, which is a typical end class to use in a program if one is not planning to do any graphical overplotting. The figure key indicates the base class verses the widget specific classes.

The View classes are rooted in the base class ImageView, which handles image display, scaling (zooming), panning, manual cut levels, auto cut levels, color mapping, transformations, and rotation. The ImageView is quite powerful compared to base classes in most inheritance designs, as it actually renders the view all the way out to RGB image planes in the appropriate sizes for the widget target window. Ginga supports "backends" for different widget sets (Gtk, Qt, Tk, etc.) through various subclasses of this base class, which do the actual painting of the resulting RGB image into a widget in the native widget set.

In this example, ImageViewXYZ is a class that renders to a native widget in the "XYZ" toolkit. ImageViewEvent adds event handlers for various pointing and keyboard events, but without connecting them to any particular handling scheme. Finally, ImageViewZoom provides a concrete implementation of event handling by connecting the handlers in the ImageViewEvent class with the logic in the BindingMapper and Bindings delegate objects as will as some logic in the UIMixin class. This event handling scheme is described in more detail in the section on the Controller. With this layered class construction, it is possible to minimize the widget specific code and reuse a large amount of code across widget sets and platforms. Because the vast majority of work is done in the base class, and the outer classes simply inherit the widget-specific ones and mix in the others, it is a fairly simple matter to port the basic Ginga functionality to a new widget set. All that is required is that the new widget set have some kind of native widget that supports painting an RGB image (like a canvas or image widget) and a way to register for user interaction events on that widget.

### **The Controller**

The control interface is a combination of methods on the view object and a pluggable Bindings class which handles the mapping of user input events such as mouse, gesture and keystrokes into commands on the view. There are many callback functions that can be registered, allowing the user to create their own custom user interface for manipulating the view.

### 5.7.2 Graphics on Ginga




Fig. 8: Class structure of Ginga DrawingCanvas class.

Ginga's graphics are all rendered from objects placed on a DrawingCanvas. All objects that can be put on a DrawingCanvas are rooted in the CanvasObject type (including DrawingCanvas itself).

### 5.7.3 Miscellaneous Topics

### I want to use my own World Coordinate System!

No problem. Ginga encapsulates the WCS behind a pluggable object used in the AstroImage class. Your WCS should implement this abstract class:

```
def MyWCS(object):
    def __init__(self, logger):
        self.logger = logger
    def get_keyword(self, key):
        return self.header[key]
    def get_keywords(self, *args):
        return [self.header[key] for key in args]
    def load_header(self, header, fobj=None):
        pass
    def pixtoradec(self, idxs, coords='data'):
        # calculate ra_deg, dec_deg
        return (ra_deg, dec_deg)
```

To use your WCS with Ginga create your images like this:

```
from ginga.AstroImage import AstroImage
AstroImage.set_wcsClass(MyWCS)
...
image = AstroImage()
...
view.set_image(image)
```

or you can override the WCS on a case-by-case basis:

```
from ginga.AstroImage import AstroImage
...
image = AstroImage(wcsclass=MyWCS)
...
view.set_image(image)
```

You could also subclass AstroImage or BaseImage and implement your own WCS handling. There are certain methods in AstroImage used for graphics plotting and plugins, however, so these would need to be supported if you expect the same functionality.

#### I want to use my own file storage format, not FITS!

First of all, you can always create an AstroImage and assign its components for wcs and data explicitly. Assuming you have your data loaded into an numpy array named data:

```
from ginga import AstroImage
...
image = AstroImage()
image.set_data(data)
```

To create a valid WCS for this image, you can set the header in the image (this assumes header is a valid mapping of keywords to values):

```
image.update_keywords(header)
```

An AstroImage can then be loaded into a viewer object with set\_dataobj(). If you need a custom WCS see the notes in Section *I want to use my own World Coordinate System!*. If, however, you want to add a new type of custom loader into Ginga's file loading framework, you can do so using the following instructions.

#### Adding a new kind of file opener

Ginga's general file loading facility breaks the loading down into two phases: first, the file is identified by its magic signature (requires the optional Python module python-magic be installed), MIME type, or filename extension. Once the general category of file is known, methods in the specific I/O module devoted to that type are called to load the file data.

The ginga.util.loader module is used to register file openers. An opener is a class that understand how to load data objects from a particular kind of file format. You'll want to start by examining this module and especially looking at the examples at the bottom of that file for how openers are registered.

For implementing your own special opener, take a look at the BaseIOHandler class in ginga.util.io. io\_base. This is the base class for all I/O openers for Ginga. Subclass this class, and implement all of the methods that raise NotImplementedError and optionally implement any other methods marked with the comment "subclass should override as needed". You can study the io\_fits and io\_rgb modules to see how these methods are implemented for specific formats. Here is an example opener class for HDF5 standard image files:

```
# This is open-source software licensed under a BSD license.
# Please see the file LICENSE.txt for details.
.....
Module wrapper for loading HDF5 files.
.. note:: The API for this module is currently unstable
          and may change in a future release.
.....
import re
from collections import OrderedDict
import numpy as np
try:
    import h5py # noqa
   have_h5py = True
except ImportError:
   have_h5py = False
from ginga.util import iohelper
__all__ = ['have_h5py', 'load_file', 'HDF5FileHandler']
def load_file(filepath, idx=None, logger=None, **kwargs):
    Load an object from an H5PY file.
    See :func:`ginga.util.loader` for more info.
    .....
   opener = HDF5FileHandler(logger)
    with opener.open_file(filepath):
        return opener.load_idx(idx, **kwargs)
class HDF5FileHandler(object):
   name = 'h5py'
    def __init__(self, logger):
        if not have_h5py:
```

```
raise ValueError(
            "Need 'h5py' module installed to use this file handler")
    super(HDF5FileHandler, self).__init__()
    self.kind = 'hdf5'
    self.logger = logger
    self._f = None
def get_indexes(self):
   return self._f.keys()
def get_header(self, idx):
    items = [(key, val.decode() if isinstance(val, bytes) else val)
             for key, val in self._f[idx].attrs.items()]
    return OrderedDict(items)
def get_idx_type(self, idx):
    header = self.get_header(idx)
    if header.get('CLASS', None) in ['IMAGE']:
        return 'image'
    # TODO: is there a table spec for HDF5?
    return None
def load_idx(self, idx, **kwargs):
    if idx is None:
        idx = self.find_first_good_idx()
    typ = self.get_idx_type(idx)
    if typ == 'image':
        from ginga import AstroImage, RGBImage
       header = self.get_header(idx)
        data_np = np.copy(self._f[idx].value)
        if 'PALETTE' in header:
            p_idx = header['PALETTE']
            p_data = self._f[p_idx].value
            data_np = p_data[data_np]
            image = RGBImage.RGBImage(logger=self.logger)
        else:
            image = AstroImage.AstroImage(logger=self.logger)
            image.update_keywords(header)
        image.set_data(data_np)
        name = iohelper.name_image_from_path(self._path, idx=idx)
        image.set(path=self._path, name=name, idx=idx,
                  image_loader=load_file)
        return image
    raise ValueError("I don't know how to read dataset '{}'".format(idx))
```

```
def open_file(self, filespec, **kwargs):
    # open the HDF5 file and make a full inventory of what is
    # available to load
   info = iohelper.get_fileinfo(filespec)
    if not info.ondisk:
        raise ValueError("File does not appear to be on disk: %s" % (
            info.url))
    self._path = info.filepath
    self.logger.debug("Loading file '%s' ..." % (self._path))
    self._f = h5py.File(self._path, 'r', **kwargs)
    return self
def close(self):
    _f = self._f
   self._f = None
   self._path = None
   _f.close()
def __len_(self):
    if self._f is None:
        return 0
    return len(self._f)
def __enter__(self):
   return self
def __exit__(self, exc_type, exc_val, exc_tb):
   self.close()
    return False
def load_idx_cont(self, idx_spec, loader_cont_fn, **kwargs):
    if len(self) == 0:
        raise ValueError("Please call open_file() first!")
    idx_lst = self.get_matching_indexes(idx_spec)
    for idx in idx_lst:
       try:
            dst_obj = self.load_idx(idx, **kwargs)
            # call continuation function
            loader_cont_fn(dst_obj)
        except Exception as e:
            self.logger.error("Error loading index '%s': %s" % (idx, str(e)))
def find_first_good_idx(self):
    for idx in self.get_indexes():
        # rule out Datasets we can't deal with
        typ = self.get_idx_type(idx)
        if typ not in ('image', 'table'):
            continue
        # Looks good, let's try it
```

```
return idx
    return None
def get_matching_indexes(self, idx_spec):
    .....
    Parameters
    _____
    idx_spec : str
       A string in the form of a pair of brackets enclosing some
        index expression matching Datasets in the file
    Returns
    _____
    result : list
       A list of indexes that can be used to access each Dataset
        matching the pattern
    .....
    # if index is missing, assume to open the first Dataset we know how
    # to do something with
    if idx_spec is None or idx_spec == '':
        idx = self.find_first_good_idx()
        return [idx]
    match = re.match(r'^\[(.+)\]$', idx_spec)
    if not match:
        return []
    name = match.group(1).strip()
    if re.match(r'^\d+$', name):
        # index just names a single dataset by number
        # Assume this means by order in the list
        return [int(name)]
    # find all datasets matching the name
    # TODO: could do some kind of regular expression matching
    idx_lst = []
    idx = 0
    for d_name in self.get_indexes():
        if name == '*' or name == d_name:
            idx_lst.append(d_name)
    return idx_lst
```

Once you have created your opener class (e.g. HDF5FileHandler), you register it as follows:

```
from ginga.util import loader
import io_hdf5
loader.add_opener(io_hdf5.HDF5FileHandler, ['application/x-hdf'])
```

If you want to use this with the Ginga reference viewer, a good place to register the opener is in your ginga\_config.py as discussed in Section *Customizing the Layout* of the Reference Viewer Manual. The best place is probably by implementing pre\_gui\_config and registering it as shown above in that function. Once your loader is registered, you will be able to drag and drop files and use the reference viewers regular loading facilities to load your data.

## Porting Ginga to a New Widget Set

[TBD]

# CHAPTER

# **OPTIMIZING PERFORMANCE**

There are several ways to optimize the performance of certain aspects of Ginga's operation.

# 6.1 **OpenCL Acceleration**

Ginga includes support for OpenCL accelerated array operations for some operations (e.g. rotation). This support is not enabled by default.

To enable OpenCL support, install the pyopencl module, e.g.:

```
pip install pyopencl
```

If you are building your own program using a ginga viewer widget, simply enable the support by:

```
from ginga import trcalc
trcalc.use('opencl')
```

If you are using the reference viewer, you can add the command line option --opencl to enable support.

Alternatively, you can add the following line to your Ginga general options configuration file (\$HOME/.ginga/general.cfg):

use\_opencl = **True** 

**Note:** pyopencl may prompt you if it can't figure out which device is the obvious choice to use as for hardware acceleration. If so, you can set the PYOPENCL\_CTX variable to prevent being prompted in the future.

Example of being prompted by pyopencl package:

```
$ ginga
NVIDIA: no NVIDIA devices found
Choose platform:
[0] <pyopencl.Platform 'Intel(R) OpenCL' at 0x2d95fd0>
[1] <pyopencl.Platform 'Clover' at 0x7f13f3ffcac0>
Choice [0]:
Set the environment variable PYOPENCL_CTX='' to avoid
being asked again.
```

# 6.2 OpenCv Acceleration

Ginga includes support for OpenCv accelerated operations (e.g. rotation and rescaling). This support is not enabled by default.

To enable OpenCv support, install the python opencv module (you can find it here).

If you are building your own program using a ginga viewer widget, simply enable the support by:

```
from ginga import trcalc
trcalc.use('opencv')
```

If you are using the reference viewer, you can add the command line option --opencv to enable support.

Alternatively, you can add the following line to your Ginga general options configuration file (\$HOME/.ginga/general.cfg):

use\_opencv = **True** 

# 6.3 numexpr Acceleration

Ginga can use the numexpr package to speed up rotations. However, this is only used if the OpenCL and OpenCv optimizations are not being used and the performance gain is not nearly as dramatic as with the latter.

To enable numexpr acceleration, simply install the package, e.g.:

pip install numexpr

It will be automatically detected and used when appropriate.

# SEVEN

# FAQS

This section contains some frequently asked questions (FAQs) regarding Ginga usage.

# 7.1 Platforms

# 7.1.1 Does Ginga run on Mac/Windows/Linux/XYZ?

Ginga is written entirely in the Python programming language, and uses only supporting Python packages. As long as a platform supports Python and the necessary packages, it can run some version of Ginga. On recent Linux, Mac and Windows versions, all of these packages are available.

# 7.1.2 Does Ginga work with Python 3?

Yes, but only Python 3.5 or later. Just install with Python 3. Of course, you need all the supporting modules for Python 3 (NumPy, SciPy, Qt 5, etc.).

# 7.1.3 Does Ginga work with Python 2?

No. If you absolutely have to use Python 2, please downgrade to Ginga 2.x series.

# 7.2 Toolkits

## 7.2.1 What GUI toolkit does Ginga use?

It depends what exactly you want to run. Ginga is both a toolkit for building viewers and also includes a "reference viewer". The example programs currently support Qt, GTK, Tk, matplotlib and web browser via HTML5 canvas. Some other toolkits are being worked on and may be partially supported.

The full reference viewer currently supports Qt (4, 5 and PySide) and Gtk (ver 3). The difference is explained here, in Section *Developing with Ginga*.

# 7.3 Control Bindings

# 7.3.1 Can I get DS9-like user interface mappings?

Save the file called bindings.cfg.ds9 and drop it in your \$HOME/.ginga folder as "bindings.cfg". Then restart Ginga.

# 7.3.2 Can I customize the user interface mappings?

Yes. There is more information in the Binding Config File section.

# 7.3.3 Where can I find a quick reference of the bindings?

See Section Quick Reference.

# 7.4 Miscellaneous

# 7.4.1 Does Ginga work with SAMP?

Yes. See Section SAMP Control.

# 7.4.2 Is it possible to control Ginga remotely?

Yes. See Section RC.

# 7.4.3 When are you going to add the XYZ feature that DS9 has?

Maybe never. The Ginga package design goal was never to replace DS9, but to provide a full featured Python FITS widget that we could use to build directly in Python. This is clearly seen if you look at the example programs in examples/\*/example\*.py. The idea was to make it easy for someone to build any kind of custom viewer by having a full-featured widget to build on.

That said, we did write a reference viewer because we needed something with many of the convenience features of a modern FITS viewer. DS9 is almost the size of a small OS, however, and I'm not sure it is wise to try to match it feature for feature. Instead, since Ginga is plugin-based, you can write plugins to give you the features you need. DS9 is a "everything including kitchen sink" kind of viewer, whereas ginga reference viewer is more like a "take what you need from the pantry and whip it up" type viewer.

Please send a pull request!

# 7.4.4 Can I get Ginga reference viewer to save its size and position?

Yes. Add the line "save\_layout = True" to your ~/.ginga/general.cfg file. If the file does not exist, create it, or copy the one from ginga/examples/configs/general.cfg.

# 7.5 World Coordinate System

# 7.5.1 What library are you using for WCS?

We are lucky to have several possible choices for a Python WCS package compatible with Ginga: AstLib, Kapteyn, Starlink, and Astropy WCS.

Kapteyn and Astropy wrap Mark Calabretta's "WCSLIB", AstLib wraps Jessica Mink's "wcstools", and I'm not sure what Starlink uses. Note that AstLib and Starlink require Astropy to be installed in order to create a WCS object from a FITS header.

To force the use of a particular one add this to your "general.cfg" in \$HOME/.ginga:

WCSpkg = 'package'

Replace 'package' with one of 'Astropy', 'Kapteyn', 'Starlink', 'astlib', or 'choose'. If you pick 'choose', Ginga will try to pick one for you.

## 7.5.2 How easy is it for Ginga to support a custom WCS?

Pretty easy. See Section I want to use my own World Coordinate System!.

# 7.6 I/O and File Formats

# 7.6.1 What library are you using for FITS I/O?

There are two possible choices for a Python FITS file reading package compatible with Ginga: Astropy FITS and fitsio. Both are originally based on the CFITSIO library (although Astropy's version uses very little of it any more, while fitsio is still tracking the current version).

To force the use of a particular one add this to your "general.cfg" in \$HOME/.ginga:

FITSpkg = 'package'

Replace 'package' with one of 'Astropy', 'fitsio', or 'choose'. If you pick 'choose', Ginga will try to pick one for you.

# 7.6.2 How easy is it for Ginga to support a new file formats besides FITS?

Pretty easy. See Section I want to use my own file storage format, not FITS!.

# 7.7 Problems Displaying Images

Nothing changes in the image when I change settings under "Preferences".

**Note:** The Preferences plugin sets the preferences on a *per-channel* basis. Make sure the channel you are looking at has the same name as the prefix for the preferences. For example: "Image" and "Image: Preferences" or "Image1" and "Image1: Preferences".

The preferences for a given channel are copied from the default "Image" channel until they are explicitly set and saved using this plugin. So if you want preferences that follow around from channel to channel, save them as preferences for "Image" and any new channels created will get those as well, unless you have saved different ones under those channel names.

Nothing changes in the image when I change the "Auto Cuts" settings under Preferences. I've checked that I'm adjusting preferences for the same channel that I'm viewing.

Note: What is the setting for "Cut New" under the New Images section in Preferences for this channel?

If that setting is "Off" then you have elected not to have Ginga apply Auto Levels when an image is loaded in that channel. Press 'a' in the image window to force an auto cut levels and it will use the new settings.

No image shows in the display, and I get an error in the terminal about histogram and keyword "density".

**Note:** You need a newer version of NumPy.

I recommend getting NumPy v1.9 or later.

# CHAPTER

# EIGHT

# **REFERENCE/API**

# 8.1 ginga.canvas.CanvasMixin Module

# 8.1.1 Classes

CanvasMixin()	A CanvasMixin is combined with the CompoundMixin
	to make a tag-addressible canvas-like interface.

## CanvasMixin

class ginga.canvas.CanvasMixin.CanvasMixin
 Bases: object

A CanvasMixin is combined with the CompoundMixin to make a tag-addressible canvas-like interface. This mixin should precede the CompoundMixin in the inheritance (and so, method resolution) order.

## **Methods Summary**

add(obj[, tag, tagpfx, belowThis, redraw])
deleteAllObjects([redraw])
<pre>deleteObject(obj[, redraw])</pre>
<pre>deleteObjectByTag(tag[, redraw])</pre>
<pre>deleteObjects(objects[, redraw])</pre>
<pre>deleteObjectsByTag(tags[, redraw])</pre>
<pre>delete_all_objects([redraw])</pre>
<pre>delete_object(obj[, redraw])</pre>
<pre>delete_object_by_tag(tag[, redraw])</pre>
delete_objects(objects[, redraw])
<pre>delete_objects_by_tag(tags[, redraw])</pre>
getObjectByTag(tag)
getObjectsByTagpfx(tagpfx)
getTagsByTagpfx(tagpfx)
get_object_by_tag(tag)
get_objects_by_tag_pfx(tagpfx)
get_tags()
get_tags_by_tag_pfx(tagpfx)
continues on next page

has_tag(tag)		
lookup_object_tag(obj)		
<pre>lowerObjectByTag(tag[, belowThis, redraw])</pre>		
<pre>lower_object_by_tag(tag[, belowThis, re-</pre>		
draw])		
<pre>raiseObjectByTag(tag[, aboveThis, redraw])</pre>		
<pre>raise_object_by_tag(tag[, aboveThis, re-</pre>		
draw])		
redraw([whence])		
<pre>subcanvas_updated_cb(canvas, whence)</pre>	This is a notification that a subcanvas (a canvas con-	
	tained in our canvas) has been modified.	
update canvas([whence])		

### Table 2 - continued from previous page

### **Methods Documentation**

**add** (*obj*, *tag=None*, *tagpfx=None*, *belowThis=None*, *redraw=True*) deleteAllObjects(redraw=True) **deleteObject** (*obj*, *redraw=True*) deleteObjectByTag(tag, redraw=True) deleteObjects (objects, redraw=True) deleteObjectsByTag (tags, redraw=True) delete\_all\_objects(redraw=True) delete\_object (obj, redraw=True) delete\_object\_by\_tag(tag, redraw=True) delete\_objects (objects, redraw=True) delete\_objects\_by\_tag(tags, redraw=True) getObjectByTag(tag) getObjectsByTagpfx(tagpfx) getTagsByTagpfx(*tagpfx*) get\_object\_by\_tag(tag) get\_objects\_by\_tag\_pfx(*tagpfx*) get\_tags() get\_tags\_by\_tag\_pfx(tagpfx) has\_tag(tag) lookup\_object\_tag(obj) lowerObjectByTag(tag, belowThis=None, redraw=True) lower\_object\_by\_tag(tag, belowThis=None, redraw=True) raiseObjectByTag(tag, aboveThis=None, redraw=True) raise\_object\_by\_tag(tag, aboveThis=None, redraw=True) redraw(whence=3)

subcanvas\_updated\_cb(canvas, whence)

This is a notification that a subcanvas (a canvas contained in our canvas) has been modified. We in turn signal that our canvas has been modified.

update\_canvas(whence=3)

# 8.2 ginga.canvas.CanvasObject Module

# 8.2.1 Functions

get_canvas_type(name)	
get_canvas_types()	
<pre>register_canvas_type(name, klass)</pre>	
<pre>register_canvas_types(klass_dict)</pre>	

### get\_canvas\_type

ginga.canvas.CanvasObject.get\_canvas\_type(name)

### get\_canvas\_types

ginga.canvas.CanvasObject.get\_canvas\_types()

### register\_canvas\_type

ginga.canvas.CanvasObject.register\_canvas\_type (name, klass)

### register\_canvas\_types

ginga.canvas.CanvasObject.register\_canvas\_types(klass\_dict)

## 8.2.2 Classes

CanvasObjectBase(**kwdargs)	This is the abstract base class for a CanvasObject.
-----------------------------	---

### **CanvasObjectBase**

class ginga.canvas.CanvasObject.CanvasObjectBase(\*\*kwdargs)
 Bases: ginga.misc.Callback.Callbacks

This is the abstract base class for a CanvasObject. A CanvasObject is an item that can be placed on a ImageViewCanvas.

This class defines common methods used by all such objects.

# **Methods Summary**

<pre>calc_dual_scale_from_pt(pt, detail)</pre>	
calc_radius(viewer, p1, p2)	
calc_rotation_from_pt(pt, detail)	
calc_scale_from_pt(pt, detail)	
calc_vertexes(start_cx, start_cy, end_cx,	
end_cy)	
canvascoords(viewer, data_x, data_y[, center])	
contains(x, y)	For backward compatibility.
<pre>contains_arr(x_arr, y_arr)</pre>	For backward compatibility.
contains_pt(pt)	
<pre>contains_pts(points)</pre>	
<pre>convert_mapper(tomap)</pre>	Converts our object from using one coordinate map
convere_mapper(comp)	to another.
draw_arrowhead(cr, x1, y1, x2, y2)	
draw_caps(cr, cap, points[, radius])	
draw_edit(cr, viewer)	
get_bbox([points])	Get bounding box of this object.
get_center_pt()	Return the geometric average of points as
	data_points.
<pre>get_cpoints(viewer[, points, no_rotate])</pre>	uum_pomo.
get_data(*args)	
get_data_points([points])	Points returned are in data coordinates.
get_move_scale_rotate_pts(viewer)	Returns 3 edit control points for editing this object:
<u> </u>	a move point, a scale point and a rotate point.
	r in r
<pre>get_point_by_index(i)</pre>	
	Get the set of points that is used to draw the object.
get_pt(viewer, points, pt[, canvas_radius])	Takes an array of points points and a target point
	pt.
	1
initialize(canvas, viewer, logger)	
is_compound()	
<pre>move_delta(xoff, yoff)</pre>	For backward compatibility.
move_delta_pt(off_pt)	
move_to(xdst, ydst)	For backward compatibility.
<pre>move_to_pt(dst_pt)</pre>	
point_within_line(points, p_start, p_stop,	
)	
point_within_radius(points, pt, can-	Points points and point pt are in data coordinates.
vas_radius)	
rerotate_by_deg(thetas, detail)	
rescale_by(scale_x, scale_y, detail)	For backward compatibility.
rescale_by_factors(factors, detail)	1 7
<pre>rotate(theta_deg[, xoff, yoff])</pre>	For backward compatibility.
rotate_by(theta_deg)	For backward compatibility.
rotate_by_deg(thetas)	1 2
rotate_deg(thetas, offset)	
scale_by(scale_x, scale_y)	For backward compatibility.
scale_by_factors(factors)	

scale_font(viewer)	
<pre>select_contains(viewer, x, y)</pre>	For backward compatibility.
<pre>select_contains_pt(viewer, pt)</pre>	
set_data(**kwdargs)	
<pre>set_data_points(points)</pre>	Input points must be in data coordinates, will be converted to the coordinate space of the object and stored.
<pre>set_point_by_index(i, pt)</pre>	
setup_edit(detail)	subclass should override as necessary.
<i>swapxy</i> (x1, y1, x2, y2)	
sync_state()	This method called when changes are made to the parameters.
use_coordmap(mapobj)	
<pre>within_line(viewer, points, p_start, p_stop,)</pre>	<b>Points</b> points and line endpoints p_start, p_stop are in data coordinates.
within_radius(viewer, points, pt, can- vas_radius)	Points points and point pt are in data coordinates.

<b>—</b>				•	
DIDID	5 -	CONTINUED	trom	nravinie	nana
Iable	5-	continued	ILOILI	DIEVIOUS	Daue

### **Methods Documentation**

calc\_dual\_scale\_from\_pt (pt, detail)

calc\_radius (viewer, p1, p2)

calc\_rotation\_from\_pt (pt, detail)

calc\_scale\_from\_pt (pt, detail)

**calc\_vertexes** (*start\_cx*, *start\_cy*, *end\_cx*, *end\_cy*, *arrow\_length=10*, *arrow\_degrees=0.35*)

**canvascoords** (*viewer*, *data\_x*, *data\_y*, *center=None*)

#### **contains** (x, y)

For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use contains\_pt() instead.

### contains\_arr (x\_arr, y\_arr)

For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use contains\_pts() instead.

### contains\_pt(pt)

#### contains\_pts (points)

### convert\_mapper(tomap)

Converts our object from using one coordinate map to another.

NOTE: In some cases this only approximately preserves the equivalent point values when transforming between coordinate spaces.

```
draw_arrowhead (cr, x1, y1, x2, y2)
```

```
draw_caps (cr, cap, points, radius=None)
```

draw\_edit (cr, viewer)

**get\_bbox** (*points=None*) Get bounding box of this object.

Returns

(p1, p2, p3, p4): a 4-tuple of the points in data coordinates,

### beginning with the lower-left and proceeding counter-clockwise.

### get\_center\_pt()

Return the geometric average of points as data\_points.

get\_cpoints (viewer, points=None, no\_rotate=False)

- get\_data(\*args)
- get\_data\_points (points=None)

Points returned are in data coordinates.

get\_move\_scale\_rotate\_pts(viewer)

Returns 3 edit control points for editing this object: a move point, a scale point and a rotate point. These points are all in data coordinates.

get\_num\_points()

```
get_point_by_index(i)
```

### get\_points()

Get the set of points that is used to draw the object.

Points are returned in *data* coordinates.

get\_pt (viewer, points, pt, canvas\_radius=None)

Takes an array of points points and a target point pt. Returns the first index of the point that is within the radius of the target point. If none of the points are within the radius, returns None.

get\_reference\_pt()

initialize (canvas, viewer, logger)

is\_compound()

```
move_delta (xoff, yoff)
For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use move_delta_pt instead.
```

move\_delta\_pt(off\_pt)

```
move_to (xdst, ydst)
For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use move_to_pt() instead.
```

move\_to\_pt(dst\_pt)

point\_within\_line (points, p\_start, p\_stop, canvas\_radius)

point\_within\_radius (points, pt, canvas\_radius, scales=1.0, 1.0)

Points points and point pt are in data coordinates. Return True for points within the circle defined by a center at point pt and within canvas\_radius.

rerotate\_by\_deg(thetas, detail)

**rescale\_by** (*scale\_x, scale\_y, detail*) For backward compatibility. TO BE DEPRECATED–DO NOT USE. Use rescale\_by\_factors() instead.

rescale\_by\_factors (factors, detail)

```
rotate (theta_deg, xoff=0, yoff=0)
```

For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use rotate\_deg() instead.

rotate\_by (theta\_deg)

For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use rotate\_by\_deg() instead.

rotate\_by\_deg(thetas)

rotate\_deg(thetas, offset)

scale\_by (scale\_x, scale\_y)

For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use scale\_by\_factors() instead.

scale\_by\_factors (factors)

```
scale_font (viewer)
```

```
select_contains(viewer, x, y)
```

For backward compatibility. TO BE DEPRECATED-DO NOT USE. Use select\_contains\_pt() instead.

select\_contains\_pt (viewer, pt)

set\_data(\*\*kwdargs)

```
set_data_points (points)
```

Input points must be in data coordinates, will be converted to the coordinate space of the object and stored.

 $\texttt{set\_point\_by\_index}(i, pt)$ 

```
setup_edit (detail)
```

subclass should override as necessary.

**swapxy** (*x1*, *y1*, *x2*, *y2*)

### sync\_state()

This method called when changes are made to the parameters. subclasses should override if they need any special state handling.

```
use_coordmap(mapobj)
```

### within\_line (viewer, points, p\_start, p\_stop, canvas\_radius)

Points points and line endpoints p\_start, p\_stop are in data coordinates. Return True for points within the line defined by a line from p\_start to p\_end and within canvas\_radius. The distance between points is scaled by the viewer's canvas scale.

### within\_radius (viewer, points, pt, canvas\_radius)

Points points and point pt are in data coordinates. Return True for points within the circle defined by a center at point pt and within canvas\_radius. The distance between points is scaled by the canvas scale.

# 8.3 ginga.canvas.CompoundMixin Module

# 8.3.1 Classes

CompoundMixin()	A CompoundMixin is a mixin class that makes an object
	that is an aggregation of other objects.

## CompoundMixin

```
class ginga.canvas.CompoundMixin.CompoundMixin
    Bases: object
```

A CompoundMixin is a mixin class that makes an object that is an aggregation of other objects.

It is used to make generic compound drawing types as well as (for example) layers of canvases on top of an image.

## **Methods Summary**

<pre>addObject(obj[, belowThis])</pre>	
<pre>add_object(obj[, belowThis])</pre>	
contains_pts(pts)	
deleteAllObjects()	
deleteObject(obj)	
deleteObjects(objects)	
delete_all_objects()	
delete_object(obj)	
delete_objects(objects)	
draw(viewer)	
getItemsAt(pt)	
getObjects()	
get_center_pt()	
<pre>get_edit_points(viewer)</pre>	
get_items_at(pt)	
get_llur()	Get lower-left and upper-right coordinates of the
	bounding box of this compound object.
get_objects()	
<pre>get_objects_by_kind(kind)</pre>	
<pre>get_objects_by_kinds(kinds)</pre>	
get_points()	
<pre>get_reference_pt()</pre>	
has_object(obj)	
inherit_from(obj)	
initialize(canvas, viewer, logger)	
is_compound()	
lowerObject(obj[, belowThis])	
<pre>lower_object(obj[, belowThis])</pre>	
<pre>move_delta_pt(off_pt)</pre>	
raiseObject(obj[, aboveThis])	
<pre>raise_object(obj[, aboveThis]) </pre>	
<pre>roll_objects(n) rotate(theta[, xoff, yoff])</pre>	
<pre>scale_by_factors(factors) select_contains_pt(viewer, pt)</pre>	
select_items_at(viewer, pt[, test])	
<pre>setAttrAll(**kwdargs) set_attr_all(**kwdargs)</pre>	
swap_objects()	

### Table 7 – continued from previous page

use\_coordmap(mapobj)

### **Methods Documentation**

addObject (obj, belowThis=None)

add\_object (obj, belowThis=None)

contains\_pts(pts)

deleteAllObjects()

deleteObject (*obj*)

deleteObjects (objects)

delete\_all\_objects()

delete\_object(*obj*)

delete\_objects(objects)

draw (viewer)

```
getItemsAt (pt)
```

getObjects()

```
get_center_pt()
```

```
get_edit_points(viewer)
```

```
get_items_at (pt)
```

#### get\_llur()

Get lower-left and upper-right coordinates of the bounding box of this compound object.

#### Returns

### x1, y1, x2, y2: a 4-tuple of the lower-left and upper-right coords

```
get_objects()
```

```
get_objects_by_kind(kind)
```

```
get_objects_by_kinds(kinds)
```

get\_points()

```
get_reference_pt()
```

has\_object (*obj*)

```
inherit_from(obj)
```

initialize (canvas, viewer, logger)

is\_compound()

lowerObject (obj, belowThis=None)

lower\_object (obj, belowThis=None)

move\_delta\_pt (off\_pt)

raiseObject (obj, aboveThis=None)

raise\_object (obj, aboveThis=None)
roll\_objects (n)
rotate (theta, xoff=0, yoff=0)
scale\_by\_factors (factors)
select\_contains\_pt (viewer, pt)
select\_items\_at (viewer, pt, test=None)
setAttrAll (\*\*kwdargs)
set\_attr\_all (\*\*kwdargs)
swap\_objects ()
use\_coordmap (mapobj)

# 8.4 ginga.canvas.coordmap Module

# 8.4.1 Classes

NativeMapper(viewer)	A coordinate mapper that maps to the viewer's canvas
	in the viewer's canvas coordinates.
WindowMapper(viewer)	A coordinate mapper that maps to the viewer in 'win-
	dow' coordinates.
PercentageMapper(viewer)	A coordinate mapper that maps to the viewer in 'per-
	centage' coordinates.
CartesianMapper(viewer)	A coordinate mapper that maps to the viewer in Carte-
	sian coordinates that do not scale (unlike DataMapper).
DataMapper(viewer)	A coordinate mapper that maps to the viewer in data
	coordinates.
OffsetMapper(viewer, refobj)	A coordinate mapper that maps to the viewer in data co-
	ordinates that are offsets relative to some other reference
	object.
WCSMapper(viewer)	A coordinate mapper that maps to the viewer in WCS
	coordinates.

## **NativeMapper**

**class** ginga.canvas.coordmap.**NativeMapper**(*viewer*) Bases: ginga.canvas.coordmap.BaseMapper

A coordinate mapper that maps to the viewer's canvas in the viewer's canvas coordinates.

## **Methods Summary**

data_to(data_pts[, viewer])	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
rotate_pt(pts, theta, offset)	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
to_data(cvs_pts[, viewer])	

## **Methods Documentation**

data\_to (data\_pts, viewer=None)

```
offset_pt (pts, offset)
```

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (cvs\_pts, viewer=None)

### **WindowMapper**

```
class ginga.canvas.coordmap.WindowMapper(viewer)
```

Bases: ginga.canvas.coordmap.BaseMapper

A coordinate mapper that maps to the viewer in 'window' coordinates.

### **Methods Summary**

data_to(data_pts[, viewer])	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
rotate_pt(pts, theta, offset)	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
to_data(cvs_pts[, viewer])	

### **Methods Documentation**

data\_to (data\_pts, viewer=None)

offset\_pt (pts, offset)

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (cvs\_pts, viewer=None)

### PercentageMapper

```
class ginga.canvas.coordmap.PercentageMapper(viewer)
Bases: ginga.canvas.coordmap.BaseMapper
```

A coordinate mapper that maps to the viewer in 'percentage' coordinates.

## **Methods Summary**

<pre>data_to(data_pts[, viewer])</pre>	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
rotate_pt(pts, theta, offset)	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
<pre>to_data(pct_pts[, viewer])</pre>	

### **Methods Documentation**

data\_to (data\_pts, viewer=None)

offset\_pt (pts, offset)

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

### rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (pct\_pts, viewer=None)

### **CartesianMapper**

```
class ginga.canvas.coordmap.CartesianMapper(viewer)
    Bases: ginga.canvas.coordmap.BaseMapper
```

A coordinate mapper that maps to the viewer in Cartesian coordinates that do not scale (unlike DataMapper).

### **Methods Summary**

data_to(data_pts[, viewer])	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
rotate_pt(pts, theta, offset)	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
<pre>to_data(crt_pts[, viewer])</pre>	

## **Methods Documentation**

data\_to (data\_pts, viewer=None)

offset\_pt (pts, offset)

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (crt\_pts, viewer=None)

## **DataMapper**

```
class ginga.canvas.coordmap.DataMapper(viewer)
```

 $Bases: \verb"ginga.canvas.coordmap.BaseMapper"$ 

A coordinate mapper that maps to the viewer in data coordinates.

## **Methods Summary**

data_to(data_pts[, viewer])	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
<pre>rotate_pt(pts, theta, offset)</pre>	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
to_data(data_pts[, viewer])	

## **Methods Documentation**

data\_to (data\_pts, viewer=None)

### offset\_pt (pts, offset)

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (data\_pts, viewer=None)

## **OffsetMapper**

```
class ginga.canvas.coordmap.OffsetMapper(viewer, refobj)
    Bases: ginga.canvas.coordmap.BaseMapper
```

A coordinate mapper that maps to the viewer in data coordinates that are offsets relative to some other reference object.

### **Methods Summary**

calc_offsets(pts)	
data_to(data_pts[, viewer])	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
rotate_pt(pts, theta, offset)	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
to_data(delta_pt[, viewer])	

### **Methods Documentation**

### calc\_offsets (pts)

data\_to (data\_pts, viewer=None)

offset\_pt (pts, offset)

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (delta\_pt, viewer=None)

### **WCSMapper**

class ginga.canvas.coordmap.WCSMapper(viewer)

Bases: ginga.canvas.coordmap.BaseMapper

A coordinate mapper that maps to the viewer in WCS coordinates.

### **Methods Summary**

<pre>data_to(data_pts[, viewer])</pre>	
offset_pt(pts, offset)	Offset a point specified by pt, by the offsets
	offset.
rotate_pt(pts, theta, offset)	Rotate a point specified by pt by the angle theta
	(in degrees) around the point indicated by offset.
<pre>to_data(wcs_pts[, viewer])</pre>	

## **Methods Documentation**

data\_to (data\_pts, viewer=None)

offset\_pt (pts, offset)

Offset a point specified by pt, by the offsets offset. Coordinates are assumed to be in the space defined by this mapper.

rotate\_pt (pts, theta, offset)

Rotate a point specified by pt by the angle theta (in degrees) around the point indicated by offset. Coordinates are assumed to be in the space defined by this mapper.

to\_data (wcs\_pts, viewer=None)

# 8.5 ginga.canvas.DrawingMixin Module

# 8.5.1 Classes

DrawingMixin()	The DrawingMixin is a mixin class that adds drawing capability for some of the basic CanvasObject-derived
	types.

## DrawingMixin

class ginga.canvas.DrawingMixin.DrawingMixin
 Bases: object

The DrawingMixin is a mixin class that adds drawing capability for some of the basic CanvasObject-derived types. The set\_surface method is used to associate a ImageViewCanvas object for layering on.

## **Methods Summary**

add_draw_mode(name, **kwargs)	
clear_selected()	
draw(viewer)	
draw_motion(canvas, event, data_x, data_y,)	
draw_poly_add(canvas, event, data_x, data_y,	
)	
draw_poly_delete(canvas, event, data_x,)	
draw_start(canvas, event, data_x, data_y,	
viewer)	
draw_stop(canvas, event, data_x, data_y, viewer)	
edit_delete()	
edit_delete_cb(canvas, event, data_x,)	
<pre>edit_motion(canvas, event, data_x, data_y,)</pre>	
edit_poly_add(canvas, event, data_x, data_y,	
)	
<pre>edit_poly_delete(canvas, event, data_x,)</pre>	
edit_rotate(delta_deg, viewer)	
	a sufficience and model and

edit_scale(delta_x, delta_y, viewer)
edit_select(newobj)
edit_start(canvas, event, data_x, data_y,
viewer)
edit_stop(canvas, event, data_x, data_y, viewer)
enable_draw(tf)
enable_edit(tf)
getDrawClass(drawtype)
get_draw_class(drawtype)
get_draw_classes()
get_draw_mode()
get_drawparams()
get_drawtype()
get_drawtypes()
get_edit_object()
get_selected()
is_drawing()
is_editing()
is_selected(obj)
num_selected()
pick_hover(canvas, event, data_x, data_y,
viewer)
pick_key(canvas, event, data_x, data_y, viewer)
<pre>pick_motion(canvas, event, data_x, data_y,)</pre>
<pre>pick_start(canvas, event, data_x, data_y,</pre>
viewer)
pick_stop(canvas, event, data_x, data_y, viewer)
process_drawing()
register_canvas_type(name, klass)
register_for_cursor_drawing(viewer)
select_add(obj)
select_remove(obj)
setSurface(viewer)
set_draw_mode(mode)
<pre>set_drawcolor(colorname)</pre>
<pre>set_drawtype(drawtype, **drawparams)</pre>
set_surface(viewer)

Table 17 – continued from previous page

## **Methods Documentation**

add\_draw\_mode (name, \*\*kwargs)
clear\_selected()
draw (viewer)
draw\_motion (canvas, event, data\_x, data\_y, viewer)
draw\_poly\_add (canvas, event, data\_x, data\_y, viewer)
draw\_poly\_delete (canvas, event, data\_x, data\_y, viewer)
draw\_start (canvas, event, data\_x, data\_y, viewer)

- draw\_stop (canvas, event, data\_x, data\_y, viewer)
- edit\_delete()
- edit\_delete\_cb(canvas, event, data\_x, data\_y, viewer)
- edit\_motion (canvas, event, data\_x, data\_y, viewer)
- edit\_poly\_add(canvas, event, data\_x, data\_y, viewer)
- edit\_poly\_delete (canvas, event, data\_x, data\_y, viewer)
- edit\_rotate(delta\_deg, viewer)
- edit\_scale(delta\_x, delta\_y, viewer)
- edit\_select (newobj)
- edit\_start (canvas, event, data\_x, data\_y, viewer)
- edit\_stop (canvas, event, data\_x, data\_y, viewer)
- enable\_draw(tf)
- enable\_edit(tf)
- getDrawClass (drawtype)
- get\_draw\_class (drawtype)

```
get_draw_classes()
```

- get\_draw\_mode()
- get\_drawparams()
- get\_drawtype()

```
get_drawtypes()
```

```
get_edit_object()
```

```
get_selected()
```

```
is_drawing()
```

```
is_editing()
```

```
is_selected(obj)
```

```
num_selected()
```

```
pick_hover (canvas, event, data_x, data_y, viewer)
```

```
pick_key (canvas, event, data_x, data_y, viewer)
```

```
pick_motion (canvas, event, data_x, data_y, viewer)
```

```
pick_start (canvas, event, data_x, data_y, viewer)
```

pick\_stop(canvas, event, data\_x, data\_y, viewer)

process\_drawing()

```
register_canvas_type (name, klass)
```

```
register_for_cursor_drawing(viewer)
```

```
select_add(obj)
```

```
select_remove (obj)
```

setSurface(viewer)

set\_draw\_mode(mode)

set\_drawcolor(colorname)

set\_drawtype (drawtype, \*\*drawparams)

set\_surface(viewer)

# 8.6 ginga.canvas.types.layer Module

# 8.6.1 Classes

CompoundObject(*objects, **kwdargs)	Compound object on a ImageViewCanvas.
Canvas(*objects, **kwdargs)	Class to handle canvas in Ginga.
DrawingCanvas(**kwdargs)	Drawing canvas.

### CompoundObject

```
class ginga.canvas.types.layer.CompoundObject(*objects, **kwdargs)
Bases: ginga.canvas.CompoundMixin.CompoundMixin, ginga.canvas.CanvasObject.
CanvasObjectBase
```

Compound object on a ImageViewCanvas. Parameters are the child objects making up the compound object. Objects are drawn in the order listed. Example:

This makes a point inside a circle.

### **Methods Summary**

### get\_params\_metadata()

### **Methods Documentation**

classmethod get\_params\_metadata()

### Canvas

class ginga.canvas.types.layer.Canvas(\*objects, \*\*kwdargs)
Bases: ginga.canvas.CanvasMixin.CanvasMixin, ginga.canvas.types.layer.
CompoundObject

Class to handle canvas in Ginga.

## **Methods Summary**

get\_params\_metadata()

### **Methods Documentation**


classmethod get\_params\_metadata()

## **DrawingCanvas**

```
class ginga.canvas.types.layer.DrawingCanvas(**kwdargs)
Bases: ginga.Mixins.UIMixin, ginga.canvas.DrawingMixin.DrawingMixin, ginga.
canvas.types.layer.Canvas
```

Drawing canvas.

# 8.6.2 Class Inheritance Diagram



# 8.7 ginga.ImageView Module

This module handles image viewers.

# 8.7.1 Classes

<pre>ImageViewBase([logger, rgbmap, settings])</pre>	An abstract base class for displaying images represented
	by Numpy data arrays.

### **ImageViewBase**

class ginga.ImageView.ImageViewBase(logger=None, rgbmap=None, settings=None)
Bases: ginga.misc.Callback.Callbacks

An abstract base class for displaying images represented by Numpy data arrays.

This class attempts to do as much of the image handling as possible using Numpy array manipulations (even color and intensity mapping) so that only a minimal mapping to a pixel buffer is necessary in concrete subclasses that connect to an actual rendering surface (e.g., Qt, GTK, Tk, HTML5).

### **Parameters**

logger [Logger or None] Logger for tracing and debugging. If not given, one will be created.

rgbmap [RGBMapper or None] RGB mapper object. If not given, one will be created.

settings [SettingGroup or None] Viewer preferences. If not given, one will be created.

### **Attributes Summary**

vname			
vtypes			

### **Methods Summary**

<pre>apply_profile(profile[, keylist])</pre>	Apply a profile to the viewer.
<pre>apply_profile_or_settings(image)</pre>	Apply a profile to the viewer.
<pre>auto_levels([autocuts])</pre>	Apply auto-cut levels on the image view.
<pre>auto_levels_cb(setting, value)</pre>	Handle callback related to changes in auto-cut levels.
auto_orient()	Set the orientation for the image to a reasonable de-
	fault.
canvas_changed_cb(canvas, whence)	Handle callback for when canvas has changed.
<pre>canvascoords(data_x, data_y[, center])</pre>	Same as get_canvas_xy().
capture_profile(profile)	
center_cursor()	Center the cursor in the viewer's widget, in both X
	and Y.
<pre>center_image([no_reset])</pre>	Pan to the center of the image.
check_cursor_location()	Check whether the data location of the last known
	position of the cursor has changed.
checkpoint_profile()	
clear()	Clear the displayed image.
configure(width, height)	See <pre>set_window_size().</pre>
configure_surface(width, height)	See configure().
<pre>copy_attributes(dst_fi, attrlist[, share,])</pre>	Copy interesting attributes of our configuration to an-
	other image view.
copy_to_dst(target)	Extract our image and call <pre>set_image()</pre> on the
	target with it.
<pre>cut_levels(loval, hival[, no_reset])</pre>	Apply cut levels on the image view.
<pre>cut_levels_cb(setting, value)</pre>	Handle callback related to changes in cut levels.
<pre>data_to_offset(data_x, data_y[, center])</pre>	<b>Reverse of</b> offset_to_data().
define_cursor(cname, cursor)	Define a viewer cursor under a name.
	continuos on novt pago

Table 23 – continue	Table 23 – continued from previous page	
delayed_redraw()	Handle delayed redrawing of the canvas.	
enable_auto_orient(tf)	Set auto_orient behavior.	
enable_autocenter(option)	Set autocenter behavior.	
enable_autocuts(option)	Set autocuts behavior.	
enable_autozoom(option)	Set autozoom behavior.	
get_autocenter_options()	Get all valid autocenter options.	
get_autocut_methods()	Same as ginga.AutoCuts.AutoCutsBase.	
	get_algorithms().	
get_autocuts_options()	Get all valid autocuts options.	
get_autozoom_options()	Get all valid autozoom options.	
get_bg()	Get the background color.	
get_canvas()	Get the canvas object used by this instance.	
get_canvas_image()	Get canvas image object.	
get_canvas_pt(data_pt)	Similar to get_canvas_xy(), except that it takes	
	a single array of points.	
<pre>get_canvas_xy(data_x, data_y[, center])</pre>	Reverse of get_data_xy().	
<pre>get_center()</pre>	Get image center.	
<pre>get_color_algorithms()</pre>	Get available color distribution algorithm names.	
<pre>get_coordmap(key)</pre>	Get coordinate mapper.	
get_cursor(cname)	Get the cursor stored under the name.	
get_cut_levels()	Get cut levels.	
get_data(data_x, data_y)	Get the data value at the given position.	
<pre>get_data_pct(xpct, ypct)</pre>	Calculate new data size for the given axis ratios.	
get_data_pt(win_pt)	Similar to get_data_xy(), except that it takes a	
<u> </u>	single array of points.	
get_data_size()	Get the dimensions of the image currently being dis-	
<u> </u>	played.	
<pre>get_data_xy(win_x, win_y[, center])</pre>	Get the closest coordinates in the data array to those	
	reported on the window.	
get_dataobj()	Get the image currently being displayed.	
get_datarect()	Get the approximate LL and UR corners of the dis-	
<u> </u>	played image.	
get_desired_size()	Get desired size.	
get_dims(data)	Get the first two dimensions of Numpy array data.	
get_draw_rect()	Get the coordinates in the actual data corresponding	
900_aran_1000()	to the area needed for drawing images for the current	
	zoom level and pan.	
get_fg()	Get the foreground color.	
get_image()	Get the image currently being displayed.	
<pre>get_image_as_array([order])</pre>	Get the current image shown in the viewer, with any	
900_190_00_01107 ([01001])	overlaid graphics, in a numpy array with channels as	
	needed and ordered.	
<pre>get_image_as_buffer([output, order])</pre>	Get the current image shown in the viewer, with any	
	overlaid graphics, in a IO buffer with channels as	
	needed and ordered by the back end widget.	
get_last_data_xy()	Get the last position of the cursor in data coordinates.	
get_last_win_xy()	Get the last position of the cursor in window coordi-	
900_1000_W11_AY ()	nates.	
<pre>get_limits([coord])</pre>	Get the bounding box of the viewer extents.	
get_logger()	Get the logger used by this instance.	
get_rogger() get_pan([coord])	Get pan positions.	
	continues on pext page	

Table 23 – continued from previous page

Table 23 – continued	i from previous page
get_pan_rect()	Get the coordinates in the actual data corresponding
	to the area shown in the display for the current zoom
	level and pan.
<pre>get_pixel_distance(x1, y1, x2, y2)</pre>	Calculate distance between the given pixel positions.
get_plain_image_as_widget()	Get the current image shown in the viewer, without
	any overlaid graphics, in the format of an image wid-
	get in the back end toolkit.
get_private_canvas()	Get the private canvas object used by this instance.
<pre>get_refresh_stats()</pre>	Return the measured statistics for timed refresh in-
get_tettebh_btatb()	tervals.
get_rgb_image_as_buffer([output, format,	Get the current image shown in the viewer, with any
])	overlaid graphics, in a file IO-like object encoded as
])	a bitmap graphics file.
<pre>get_rgb_image_as_bytes([format, quality])</pre>	Get the current image shown in the viewer, with any
get_tgb_tmage_as_bytes([format, quanty])	-
	overlaid graphics, in the form of a buffer in the form
	of bytes.
<pre>get_rgb_image_as_widget([output, format,</pre>	Get the current image shown in the viewer, with any
])	overlaid graphics, in the form of a image widget in
	the toolkit of the back end.
get_rgb_order()	Get RGB order.
get_rgbmap()	Get the RGB map object used by this instance.
get_rotation()	Get image rotation angle.
get_rotation_info()	Get rotation information.
get_scale()	Same as get_scale_max().
get_scale_base_xy()	Get stretch factors.
<pre>get_scale_limits()</pre>	Get scale limits.
get_scale_max()	Get maximum scale factor.
get_scale_min()	Get minimum scale factor.
get_scale_text()	Report current scaling in human-readable format.
get_scale_xy()	Get scale factors.
get_settings()	Get the settings used by this instance.
get_transforms()	Get transformations behavior.
get_vip()	Get the ViewerImageProxy object used by this in-
9 c c v r p 0	stance.
get_window_size()	Get the window size in the underlying implementa-
gec_window_size()	tion.
	Get zoom level.
get_zoom()	
get_zoom_algorithm()	Get zoom algorithm.
get_zoomrate()	Get zoom rate.
<pre>getwin_array([order, alpha, dtype])</pre>	~
<pre>getwin_buffer([order, alpha, dtype])</pre>	Same as getwin_array(), but with the output ar-
	ray converted to C-order Python bytes.
<i>icc_profile_cb</i> (setting, value)	Handle callback related to changes in output ICC
	profiles.
<pre>initialize_private_canvas(private_canvas)</pre>	Initialize the private canvas used by this instance.
<pre>interpolation_change_cb(setting, value)</pre>	Handle callback related to changes in interpolation.
invert_cmap()	Invert the color map.
is_compound()	Indicate if canvas object is a compound object.
is_redraw_pending()	Indicates whether a deferred redraw has been sched-
	uled.
make_cursor(iconpath, x, y)	Make a cursor in the viewer's native widget toolkit.
	continues on next page

Table	23 – continued from previous page

Table 23 – continued from previous page	
make_timer()	Return a timer object implemented using the back
	end.
<pre>offset_to_data(off_x, off_y[, center])</pre>	Get the closest coordinates in the data array to those
	in cartesian fixed (non-scaled) canvas coordinates.
<pre>offset_to_window(off_x, off_y)</pre>	Convert data offset to window coordinates.
onscreen_message(text[, delay, redraw])	Place a message onscreen in the viewer window.
onscreen_message_off()	Erase any message onscreen in the viewer window.
pan_cb(setting, value)	Handle callback related to changes in pan.
<pre>panset_pct(pct_x, pct_y)</pre>	Similar to set_pan(), except that pan positions
panse c_pec(pet_x; pet_y)	are determined by multiplying data dimensions with
	the given scale factors, where 1 is 100%.
<pre>panset_xy(data_x, data_y[, no_reset])</pre>	Similar to set_pan(), except that input pan posi-
pansec_xy(data_x, data_y[, no_reset])	tions are always in data space.
<pre>position_cursor(data_x, data_y)</pre>	Position the current cursor to a location defined it
position_cuisor(uata_x, uata_y)	data coords.
propare image(out ima cache whence)	This can be overridden by subclasses.
<pre>prepare_image(cvs_img, cache, whence) recalc_transforms([trcat])</pre>	Takes a catalog of transforms (trcat) and builds
recarc_cransrorms([ucat])	the chain of default transforms (treat) and builds
	dering with most backends.
[]	Redraw the canvas.
redraw([whence])	
redraw_data([whence])	Render image from RGB map and redraw private
/ ([ 1])	canvas.
redraw_now([whence])	Redraw the displayed image.
refresh_timer_cb(timer, flags)	Refresh timer callback.
reschedule_redraw(time_sec)	Reschedule redraw event.
reset_limits()	Reset the bounding box of the viewer extents.
restore_cmap()	Restores the color map from any rotation, stretch
	and/or shrinkage.
restore_contrast()	Restores the color map from any stretch and/or
	shrinkage.
rgbmap_cb(rgbmap)	Handle callback for when RGB map has changed.
rotate(deg)	Rotate the view of an image in a channel.
<pre>rotation_change_cb(setting, value)</pre>	Handle callback related to changes in rotation angle.
<pre>save_plain_image_as_file(filepath[,</pre>	Save the current image shown in the viewer, with-
format, ])	out any overlaid graphics, in a file with the specified
	format and quality.
<pre>save_profile(**params)</pre>	Save the given parameters into profile settings.
<pre>save_rgb_image_as_file(filepath[, format,</pre>	Save the current image shown in the viewer, with any
])	overlaid graphics, in a file with the specified format
	and quality.
<pre>scale_and_shift_cmap(scale_pct, shift_pct)</pre>	Stretch and/or shrink the color map.
scale_cb(setting, value)	Handle callback related to image scaling.
<pre>scale_to(scale_x, scale_y[, no_reset])</pre>	Scale the image in a channel.
set_autocenter(option)	Set autocenter behavior.
<pre>set_autocut_params(method, **params)</pre>	Set auto-cut parameters.
<pre>set_autocuts(autocuts)</pre>	Set the auto-cut algorithm.
set_background(bg)	Set the background color.
set_bg(r, g, b)	Set the background color.
set_calg(dist)	Set color distribution algorithm.
set_canvas(canvas[, private_canvas])	Set the canvas object.
set_cmap(cm)	Set color map.

Table 23 – continued from previous page

<pre>set_color_algorithm(calg_name, **kw-</pre>	
dargs)	Set the color distribution algorithm.
<pre>set_color_map(cmap_name)</pre>	Set the color map.
<pre>set_coordmap(key, mapper)</pre>	Set coordinate mapper.
set_cursor(cursor)	Set the cursor in the viewer widget.
set_data(data[, metadata])	Set an image to be displayed by providing raw data.
<pre>set_dataobj(image[, add_to_canvas])</pre>	Set an image to be displayed.
set_desired_size(width, height)	See set_window_size().
<pre>set_enter_focus(tf)</pre>	Determine whether the viewer widget should take fo-
	cus when the cursor enters the window.
<pre>set_fg(r, g, b)</pre>	Set the foreground color.
<pre>set_foreground(fg)</pre>	Set the foreground color.
<pre>set_image(image[, add_to_canvas])</pre>	Set an image to be displayed.
<pre>set_imap(im)</pre>	Set intensity map.
<pre>set_intensity_map(imap_name)</pre>	Set the intensity map.
<pre>set_limits(limits[, coord])</pre>	Set the bounding box of the viewer extents.
set_name(name)	Set viewer name.
<pre>set_onscreen_message(text[, redraw])</pre>	Called by a subclass to update the onscreen message.
<pre>set_pan(pan_x, pan_y[, coord, no_reset])</pre>	Set pan position.
set_redraw_lag(lag_sec)	Set lag time for redrawing the canvas.
<pre>set_refresh_rate(fps)</pre>	Set the refresh rate for redrawing the canvas at a
	timed interval.
<pre>set_renderer(renderer)</pre>	Set and initialize the renderer used by this instance.
<pre>set_rgbmap(rgbmap)</pre>	Set RGB map object used by this instance.
<pre>set_scale(scale[, no_reset])</pre>	Scale the image in a channel.
<pre>set_scale_base_xy(scale_x_base,</pre>	Set stretch factors.
scale_y_base)	
<pre>set_scale_limits(scale_min, scale_max)</pre>	Set scale limits.
<pre>set_window_size(width, height)</pre>	Report the size of the window to display the image.
<pre>set_zoom_algorithm(name)</pre>	Set zoom algorithm.
<pre>set_zoomrate(zoomrate)</pre>	Set zoom rate.
<pre>shift_cmap(pct)</pre>	Shift color map.
<pre>show_color_bar(tf[, side])</pre>	1
<pre>show_focus_indicator(tf[, color])</pre>	
<pre>show_mode_indicator(tf[, corner])</pre>	
<pre>show_pan_mark(tf[, color])</pre>	
<pre>start_refresh()</pre>	Start redrawing the canvas at the previously set timed interval.
<pre>stop_refresh()</pre>	Stop redrawing the canvas at the previously set timed interval.
<pre>switch_cursor(cname)</pre>	Switch the viewer's cursor to the one defined under a name.
take_focus()	Have the widget associated with this viewer take the keyboard focus.
<pre>transform(flip_x, flip_y, swap_xy)</pre>	Transform view of the image.
transform_cb(setting, value)	Handle callback related to changes in transforma- tions.
update image()	
update_image() update_widget()	Update the area corresponding to the backend wid- get.

Table 23 - continued from previous page

window_has_origin_upper()	Indicate if window of backend toolkit is imple-
	mented with an origin up or down.
<pre>window_to_offset(win_x, win_y)</pre>	Reverse of offset_to_window().
<pre>zoom_fit([no_reset])</pre>	Zoom to fit display window.
zoom_in([incr])	Zoom in a level.
zoom_out([decr])	Zoom out a level.
<pre>zoom_to(zoomlevel[, no_reset])</pre>	Set zoom level in a channel.
<pre>zoomsetting_change_cb(setting, value)</pre>	Handle callback related to changes in zoom.

Table 23 – continued from previous page

### **Attributes Documentation**

vname = 'Ginga Image'

### vtypes = [<class 'ginga.BaseImage.BaseImage'>]

### **Methods Documentation**

**apply\_profile** (*profile*, *keylist=None*) Apply a profile to the viewer.

### **Parameters**

profile [SettingGroup]

This function is used to initialize the viewer to a known state.

The keylist, if given, will limit the items to be transferred

### from the profile to viewer settings, otherwise all items are

copied.

### apply\_profile\_or\_settings (image)

Apply a profile to the viewer.

### Parameters

image [AstroImage or RGBImage] Image object.

This function is used to initialize the viewer when a new image

is loaded. Either the embedded profile settings or the default

### settings are applied as specified in the channel preferences.

auto\_levels(autocuts=None)

Apply auto-cut levels on the image view.

### Parameters

**autocuts** [subclass of AutoCutsBase or None] An object that implements the desired auto-cut algorithm. If not given, use algorithm from preferences.

auto\_levels\_cb(setting, value)

Handle callback related to changes in auto-cut levels.

### auto\_orient()

Set the orientation for the image to a reasonable default.

**canvas\_changed\_cb** (*canvas*, *whence*) Handle callback for when canvas has changed. canvascoords (data\_x, data\_y, center=None)
Same as get\_canvas\_xy().

capture\_profile (profile)

### center\_cursor()

Center the cursor in the viewer's widget, in both X and Y.

This should be implemented by subclasses.

**center\_image** (*no\_reset=True*) Pan to the center of the image.

**Parameters** 

**no\_reset** [bool] See set\_pan().

#### check\_cursor\_location()

Check whether the data location of the last known position of the cursor has changed. If so, issue a callback.

checkpoint\_profile()

#### clear()

Clear the displayed image.

configure (width, height)
 See set\_window\_size().

### configure\_surface(width, height)

See configure().

### **copy\_attributes** (*dst\_fi*, *attrlist*, *share=False*, *whence=0*)

Copy interesting attributes of our configuration to another image view.

#### **Parameters**

dst\_fi [subclass of ImageViewBase] Another instance of image view.

- attrlist [list] A list of attribute names to copy. They can be 'transforms', 'rotation', 'cutlevels', 'rgbmap', 'zoom', 'pan', 'autocuts', 'limits', 'icc' or 'interpolation'.
- **share** [bool] If True, the designated settings will be shared, otherwise the values are simply copied.

copy\_to\_dst (target)

Extract our image and call *set\_image()* on the target with it.

### Parameters

target Subclass of ImageViewBase.

**cut\_levels** (*loval*, *hival*, *no\_reset=False*) Apply cut levels on the image view.

#### **Parameters**

loval, hival [float] Low and high values of the cut levels, respectively.

no\_reset [bool] Do not reset autocuts setting.

### cut\_levels\_cb(setting, value)

Handle callback related to changes in cut levels.

# data\_to\_offset (data\_x, data\_y, center=None) Reverse of offset to data().

### define\_cursor(cname, cursor)

Define a viewer cursor under a name. Does not change the current cursor.

#### **Parameters**

**cname** [str] name of the cursor to define.

cursor [object] a cursor object in the back end's toolkit

### `cursor` is usually constructed from `make\_cursor`.

#### delayed\_redraw()

Handle delayed redrawing of the canvas.

### enable\_auto\_orient (tf)

Set auto\_orient behavior.

### **Parameters**

tf [bool] Turns automatic image orientation on or off.

### enable\_autocenter(option)

Set autocenter behavior.

### Parameters

**option** [{'on', 'override', 'once', 'off'}] Option for auto-center behavior. A list of acceptable options can also be obtained by get\_autocenter\_options().

#### Raises

### ginga.ImageView.ImageViewError Invalid option.

#### enable\_autocuts (option)

Set autocuts behavior.

### **Parameters**

**option** [{'on', 'override', 'once', 'off'}] Option for auto-cut behavior. A list of acceptable options can also be obtained by get\_autocuts\_options().

### Raises

### ginga.ImageView.ImageViewError Invalid option.

### enable\_autozoom(option)

Set autozoom behavior.

### Parameters

**option** [{'on', 'override', 'once', 'off'}] Option for zoom behavior. A list of acceptable options can also be obtained by get\_autozoom\_options().

### Raises

### ginga.ImageView.ImageViewError Invalid option.

### get\_autocenter\_options()

Get all valid autocenter options.

### Returns

autocenter\_options [tuple] A list of valid options.

### get\_autocut\_methods()

Same as ginga.AutoCuts.AutoCutsBase.get\_algorithms().

### get\_autocuts\_options()

Get all valid autocuts options.

Returns

autocuts\_options [tuple] A list of valid options.

### get\_autozoom\_options()

Get all valid autozoom options.

Returns

autozoom\_options [tuple] A list of valid options.

#### get\_bg()

Get the background color.

### Returns

img\_bg [tuple] RGB values.

### get\_canvas()

Get the canvas object used by this instance.

Returns

canvas [DrawingCanvas] Canvas.

### get\_canvas\_image()

Get canvas image object.

### Returns

imgobj [NormImage] Normalized image sitting on the canvas.

### get\_canvas\_pt(data\_pt)

Similar to get\_canvas\_xy(), except that it takes a single array of points.

get\_canvas\_xy (data\_x, data\_y, center=None)
 Reverse of get\_data\_xy().

### get\_center()

Get image center.

### Returns

ctr [tuple] X and Y positions, in that order.

### get\_color\_algorithms()

Get available color distribution algorithm names. See ginga.ColorDist.get\_dist\_names().

### get\_coordmap(key)

Get coordinate mapper.

#### Parameters

**key** [str] Name of the desired coordinate mapper.

### Returns

mapper Coordinate mapper object (see ginga.canvas.coordmap).

#### get\_cursor(cname)

Get the cursor stored under the name. This can be overridden by subclasses, if necessary.

### Parameters

cname [str] name of the cursor to return.

get\_cut\_levels()

Get cut levels.

### Returns

cuts [tuple] Low and high values, in that order.

get\_data (data\_x, data\_y)

Get the data value at the given position. Indices are zero-based, as in Numpy.

### **Parameters**

data\_x, data\_y [int] Data indices for X and Y, respectively.

### Returns

value Data value.

### get\_data\_pct (xpct, ypct)

Calculate new data size for the given axis ratios. See get\_limits().

### Parameters

**xpct**, **ypct** [float] Ratio for X and Y, respectively, where 1 is 100%.

### Returns

x, y [int] Scaled dimensions.

### get\_data\_pt(win\_pt)

Similar to get\_data\_xy(), except that it takes a single array of points.

#### get\_data\_size()

Get the dimensions of the image currently being displayed.

### Returns

size [tuple] Image dimensions in the form of (width, height).

### get\_data\_xy (win\_x, win\_y, center=None)

Get the closest coordinates in the data array to those reported on the window.

### Parameters

win\_x, win\_y [float or ndarray] Window coordinates.

**center** [bool] If True, then the coordinates are mapped such that the pixel is centered on the square when the image is zoomed in past 1X. This is the specification of the FITS image standard, that the pixel is centered on the integer row/column.

### Returns

**coord** [tuple] Data coordinates in the form of (x, y).

### get\_dataobj()

Get the image currently being displayed.

#### Returns

image [AstroImage or RGBImage] Image object.

### get\_datarect()

Get the approximate LL and UR corners of the displayed image.

### Returns

```
rect [tuple] Bounding box in data coordinates in the form of (x1, y1, x2, y2).
```

get\_desired\_size()

Get desired size.

### Returns

size [tuple] Desired size in the form of (width, height).

### get\_dims (data)

Get the first two dimensions of Numpy array data. Data may have more dimensions, but they are not reported.

### Returns

dims [tuple] Data dimensions in the form of (width, height).

### get\_draw\_rect()

Get the coordinates in the actual data corresponding to the area needed for drawing images for the current zoom level and pan. Unlike get\_pan\_rect(), this includes areas outside of the current viewport, but that might be viewed with a transformation or rotation subsequently applied.

### Returns

**points** [list] Coordinates in the form of [(x0, y0), (x1, y1), (x2, y2), (x3, y3)] corresponding to the four corners.

### get\_fg()

Get the foreground color.

### Returns

img\_fg [tuple] RGB values.

### get\_image()

Get the image currently being displayed.

### Returns

image [AstroImage or RGBImage] Image object.

### get\_image\_as\_array(order=None)

Get the current image shown in the viewer, with any overlaid graphics, in a numpy array with channels as needed and ordered.

This can be overridden by subclasses.

### get\_image\_as\_buffer(output=None, order=None)

Get the current image shown in the viewer, with any overlaid graphics, in a IO buffer with channels as needed and ordered by the back end widget.

This can be overridden by subclasses.

### Parameters

output [a file IO-like object or None] open python IO descriptor or None to have one created

### Returns

**buffer** [file IO-like object] This will be the one passed in, unless output is None in which case a BytesIO obejct is returned

### get\_last\_data\_xy()

Get the last position of the cursor in data coordinates. This can be overridden by subclasses, if necessary.

#### get\_last\_win\_xy()

Get the last position of the cursor in window coordinates. This can be overridden by subclasses, if necessary.

#### get\_limits(coord='data')

Get the bounding box of the viewer extents.

Returns

limits [tuple]

#### Bounding box in coordinates of type coord in the form of (ll\_pt, ur\_pt).

#### get\_logger()

Get the logger used by this instance.

#### Returns

#### logger [Logger] Logger.

get\_pan (coord='data')

Get pan positions.

#### Parameters

**coord** [{'data', 'wcs'}] Indicates whether the pan positions are returned in data or WCS space.

#### Returns

**positions** [tuple] X and Y positions, in that order.

#### get\_pan\_rect()

Get the coordinates in the actual data corresponding to the area shown in the display for the current zoom level and pan.

#### Returns

**points** [list] Coordinates in the form of [ (x0, y0), (x1, y1), (x2, y2), (x3, y3) ] from lower-left to lower-right.

# get\_pixel\_distance (x1, y1, x2, y2)

Calculate distance between the given pixel positions.

#### Parameters

x1, y1, x2, y2 [number] Pixel coordinates.

#### Returns

dist [float] Rounded distance.

#### get\_plain\_image\_as\_widget()

Get the current image shown in the viewer, without any overlaid graphics, in the format of an image widget in the back end toolkit. Typically used for generating thumbnails. This should be implemented by subclasses.

# Returns

widget [object] An image widget object in the viewer's back end toolkit

# get\_private\_canvas()

Get the private canvas object used by this instance.

#### Returns

canvas [DrawingCanvas] Canvas.

#### get\_refresh\_stats()

Return the measured statistics for timed refresh intervals.

#### Returns

stats [float] The measured rate of actual back end updates in frames per second.

#### get\_rgb\_image\_as\_buffer (output=None, format='png', quality=90)

Get the current image shown in the viewer, with any overlaid graphics, in a file IO-like object encoded as a bitmap graphics file.

This can be overridden by subclasses.

#### Parameters

output [a file IO-like object or None] open python IO descriptor or None to have one created

**format** [str] A string defining the format to save the image. Typically at least 'jpeg' and 'png' are supported. (default: 'png')

quality: int The quality metric for saving lossy compressed formats.

#### Returns

**buffer** [file IO-like object] This will be the one passed in, unless output is None in which case a BytesIO obejct is returned

#### get\_rgb\_image\_as\_bytes (format='png', quality=90)

Get the current image shown in the viewer, with any overlaid graphics, in the form of a buffer in the form of bytes.

#### **Parameters**

format [str] See get\_rgb\_image\_as\_buffer().

quality: int See get\_rgb\_image\_as\_buffer().

#### Returns

buffer [bytes] The window contents as a buffer in the form of bytes.

# get\_rgb\_image\_as\_widget (output=None, format='png', quality=90)

Get the current image shown in the viewer, with any overlaid graphics, in the form of a image widget in the toolkit of the back end.

#### **Parameters**

See :meth:`get\_rgb\_image\_as\_buffer`.

#### Returns

widget [object] An image widget object in the viewer's back end toolkit

#### get\_rgb\_order()

Get RGB order.

### Returns

**rgb** [str] Returns the order of RGBA planes required by the subclass to render the canvas properly.

# get\_rgbmap()

Get the RGB map object used by this instance.

#### Returns

rgbmap [RGBMapper] RGB map.

#### get\_rotation()

Get image rotation angle.

#### Returns

rot\_deg [float] Rotation angle in degrees.

#### get\_rotation\_info()

Get rotation information.

#### Returns

info [tuple] X and Y positions, and rotation angle in degrees, in that order.

#### get\_scale()

Same as get\_scale\_max().

#### get\_scale\_base\_xy()

Get stretch factors.

#### Returns

stretchfactors [tuple] Stretch factors for X and Y, in that order.

### get\_scale\_limits()

Get scale limits.

Returns

scale\_limits [tuple] Minimum and maximum scale limits, respectively.

#### get\_scale\_max()

Get maximum scale factor.

#### Returns

scalefactor [float] Scale factor for X or Y, whichever is larger.

#### get\_scale\_min()

Get minimum scale factor.

# Returns

scalefactor [float] Scale factor for X or Y, whichever is smaller.

#### get\_scale\_text()

Report current scaling in human-readable format.

#### Returns

text [str] '<num> x' if enlarged, or '1/<num> x' if shrunken.

#### get\_scale\_xy()

Get scale factors.

# Returns

scalefactors [tuple] Scale factors for X and Y, in that order.

# get\_settings()

Get the settings used by this instance.

#### Returns

settings [SettingGroup] Settings.

#### get\_transforms()

Get transformations behavior.

Returns

```
transforms [tuple] Selected options for flip_x, flip_y, and swap_xy.
```

#### get\_vip()

Get the ViewerImageProxy object used by this instance.

#### Returns

vip [ViewerImageProxy] A ViewerImageProxy object.

#### get\_window\_size()

Get the window size in the underlying implementation.

#### Returns

size [tuple] Window size in the form of (width, height).

#### get\_zoom()

Get zoom level.

#### Returns

zoomlevel [float] Zoom level.

get\_zoom\_algorithm() Get zoom algorithm.

Returns

name [str] Name of the zoom algorithm in use.

get\_zoomrate()

Get zoom rate.

Returns

zoomrate [float] Zoom rate.

getwin\_array (order='RGB', alpha=1.0, dtype=None)

getwin\_buffer (order='RGB', alpha=1.0, dtype=None)
Same as getwin\_array(), but with the output array converted to C-order Python bytes.

icc\_profile\_cb(setting, value)

Handle callback related to changes in output ICC profiles.

# initialize\_private\_canvas(private\_canvas)

Initialize the private canvas used by this instance.

#### interpolation\_change\_cb(setting, value)

Handle callback related to changes in interpolation.

#### invert\_cmap()

Invert the color map. See ginga.RGBMap.RGBMapper.invert\_cmap().

#### is\_compound()

Indicate if canvas object is a compound object. This can be re-implemented by subclasses that can overplot objects.

Returns

status [bool] Currently, this *always* returns False.

#### is\_redraw\_pending()

Indicates whether a deferred redraw has been scheduled.

#### Returns

pending [bool] True if a deferred redraw is pending, False otherwise.

#### make\_cursor(iconpath, x, y)

Make a cursor in the viewer's native widget toolkit. This should be implemented by subclasses.

#### Parameters

**iconpath** [str] the path to a PNG image file defining the cursor

x [int] the X position of the center of the cursor hot spot

y [int] the Y position of the center of the cursor hot spot

#### make\_timer()

Return a timer object implemented using the back end. This should be implemented by subclasses.

#### Returns

**timer** [a Timer object]

offset\_to\_data (off\_x, off\_y, center=None)

Get the closest coordinates in the data array to those in cartesian fixed (non-scaled) canvas coordinates.

#### Parameters

off\_x, off\_y [float or ndarray] Cartesian canvas coordinates.

Returns

**coord** [tuple] Data coordinates in the form of (x, y).

#### offset\_to\_window(off\_x, off\_y)

Convert data offset to window coordinates.

#### **Parameters**

off\_x, off\_y [float or ndarray] Data offsets.

#### Returns

**coord** [tuple] Offset in window coordinates in the form of (x, y).

#### onscreen\_message(text, delay=None, redraw=True)

Place a message onscreen in the viewer window. This must be implemented by subclasses.

#### Parameters

text [str] the text to draw in the window

**delay** [float or None] if None, the message will remain until another message is set. If a float, specifies the time in seconds before the message will be erased. (default: None)

**redraw** [bool] True if the widget should be redrawn right away (so that the message appears). (default: True)

#### onscreen\_message\_off()

Erase any message onscreen in the viewer window.

#### pan\_cb (setting, value)

Handle callback related to changes in pan.

# panset\_pct (pct\_x, pct\_y)

Similar to *set\_pan()*, except that pan positions are determined by multiplying data dimensions with the given scale factors, where 1 is 100%.

#### panset\_xy (data\_x, data\_y, no\_reset=False)

Similar to set\_pan(), except that input pan positions are always in data space.

#### position\_cursor(data\_x, data\_y)

Position the current cursor to a location defined it data coords. This should be implemented by subclasses.

#### **Parameters**

data\_x [float] the X position to position the cursor in data coords

data\_y [float] the X position to position the cursor in data coords

prepare\_image (cvs\_img, cache, whence)

This can be overridden by subclasses.

#### recalc\_transforms(trcat=None)

Takes a catalog of transforms (trcat) and builds the chain of default transforms necessary to do rendering with most backends.

### redraw(whence=0)

Redraw the canvas.

#### **Parameters**

**whence** [int or float] Optimization flag that reduces the time to refresh the viewer by only recalculating what is necessary:

0: New image, pan/scale has changed 1: Cut levels or similar has changed 2: Color mapping has changed 2.3: ICC profile has changed 2.5: Transforms have changed 2.6: Rotation has changed 3: Graphical overlays have changed

#### redraw\_data(whence=0)

Render image from RGB map and redraw private canvas.

Note: Do not call this method unless you are implementing a subclass.

#### **Parameters**

whence See redraw().

#### redraw\_now(whence=0)

Redraw the displayed image.

#### Parameters

whence See redraw().

#### refresh\_timer\_cb(timer, flags)

Refresh timer callback. This callback will normally only be called internally.

#### **Parameters**

timer [a Ginga GUI timer] A GUI-based Ginga timer

flags [dict-like] A set of flags controlling the timer

#### reschedule\_redraw(time\_sec)

Reschedule redraw event.

This should be implemented by subclasses.

#### **Parameters**

time\_sec [float] Time, in seconds, to wait.

#### reset limits()

Reset the bounding box of the viewer extents.

#### Parameters

None

#### restore\_cmap()

Restores the color map from any rotation, stretch and/or shrinkage. See ginga.RGBMap.RGBMapper. restore\_cmap().

#### restore\_contrast()

Restores the color map from any stretch and/or shrinkage. See ginga.RGBMap.RGBMapper. reset\_sarr().

rgbmap\_cb(rgbmap)

Handle callback for when RGB map has changed.

#### rotate(deg)

Rotate the view of an image in a channel.

**Note:** Transforming the image is generally faster than rotating, if rotating in 90 degree increments. Also see *transform()*.

#### **Parameters**

deg [float] Rotation angle in degrees.

#### rotation\_change\_cb (setting, value)

Handle callback related to changes in rotation angle.

#### save\_plain\_image\_as\_file (filepath, format='png', quality=90)

Save the current image shown in the viewer, without any overlaid graphics, in a file with the specified format and quality. Typically used for generating thumbnails. This should be implemented by subclasses.

#### Parameters

filepath [str] path of the file to write

format [str] See get\_rgb\_image\_as\_buffer().

quality: int See get\_rgb\_image\_as\_buffer().

#### save\_profile(\*\*params)

Save the given parameters into profile settings.

#### Parameters

params [dict] Keywords and values to be saved.

#### save\_rgb\_image\_as\_file (filepath, format='png', quality=90)

Save the current image shown in the viewer, with any overlaid graphics, in a file with the specified format and quality. This can be overridden by subclasses.

#### **Parameters**

**filepath** [str] path of the file to write

format [str] See get\_rgb\_image\_as\_buffer().

quality: int See get\_rgb\_image\_as\_buffer().

#### scale\_and\_shift\_cmap(scale\_pct, shift\_pct)

Stretch and/or shrink the color map. See ginga.RGBMap.RGBMapper.scale\_and\_shift().

#### scale\_cb (setting, value)

Handle callback related to image scaling.

#### scale\_to(scale\_x, scale\_y, no\_reset=False)

Scale the image in a channel. This only changes the viewer settings; the image is not modified in any way. Also see  $zoom_to()$ .

# Parameters

scale\_x, scale\_y [float] Scaling factors for the image in the X and Y axes, respectively.

**no\_reset** [bool] Do not reset autozoom setting.

#### set\_autocenter(option)

Set autocenter behavior.

#### **Parameters**

**option** [{'on', 'override', 'once', 'off'}] Option for auto-center behavior. A list of acceptable options can also be obtained by get\_autocenter\_options().

#### Raises

#### ginga.ImageView.ImageViewError Invalid option.

set\_autocut\_params (method, \*\*params)

Set auto-cut parameters.

#### Parameters

**method** [str] Auto-cut algorithm. A list of acceptable options can be obtained by get\_autocut\_methods().

params [dict] Algorithm-specific keywords and values.

#### set\_autocuts (autocuts)

Set the auto-cut algorithm.

### Parameters

**autocuts** [subclass of AutoCutsBase] An object that implements the desired auto-cut algorithm.

# $set\_background(bg)$

Set the background color.

#### Parameters

bg [str or tuple of float] color name or tuple of floats, between 0 and 1, inclusive.

 $set_bg(r, g, b)$ 

Set the background color.

#### Parameters

r, g, b [float] RGB values, which should be between 0 and 1, inclusive.

set\_calg(dist)

Set color distribution algorithm. See ginga.RGBMap.RGBMapper.set\_dist().

# set\_canvas(canvas, private\_canvas=None)

Set the canvas object.

#### Parameters

canvas [DrawingCanvas] Canvas object.

private\_canvas [DrawingCanvas or None] Private canvas object. If not given, this is the same as canvas.

#### set\_cmap(cm)

Set color map. See ginga.RGBMap.RGBMapper.set\_cmap().

# set\_color\_algorithm(calg\_name, \*\*kwdargs)

Set the color distribution algorithm.

Available color distribution algorithm names can be discovered using ginga.ColorDist.get\_dist\_names().

#### **Parameters**

calg\_name [str] The name of a color distribution algorithm.

kwdargs [dict] Keyword arguments for color distribution object (see ColorDist).

#### set\_color\_map(cmap\_name)

Set the color map.

Available color map names can be discovered using get\_names().

#### Parameters

**cmap\_name** [str] The name of a color map.

#### set\_coordmap (key, mapper)

Set coordinate mapper.

#### **Parameters**

**key** [str] Name of the coordinate mapper.

mapper Coordinate mapper object (see ginga.canvas.coordmap).

#### set\_cursor(cursor)

Set the cursor in the viewer widget. This should be implemented by subclasses.

# Parameters

cursor [object] a cursor object in the back end's toolkit

#### set\_data (data, metadata=None)

Set an image to be displayed by providing raw data.

This is a convenience method for first constructing an image with AstroImage and then calling set\_image().

#### **Parameters**

data [ndarray] This should be at least a 2D Numpy array.

metadata [dict or None] Image metadata mapping keywords to their respective values.

#### set\_dataobj(image, add\_to\_canvas=True)

Set an image to be displayed.

If there is no error, the 'image-unset' and 'image-set' callbacks will be invoked.

#### Parameters

image [AstroImage or RGBImage] 2D Image object.

add\_to\_canvas [bool] Add image to canvas.

# set\_desired\_size(width, height)

See set\_window\_size().

## set\_enter\_focus(tf)

Determine whether the viewer widget should take focus when the cursor enters the window.

#### **Parameters**

tf [bool] If True the widget will grab focus when the cursor moves into the window.

#### $set_fg(r, g, b)$

Set the foreground color.

#### **Parameters**

**r**, **g**, **b** [float] RGB values, which should be between 0 and 1, inclusive.

#### set\_foreground(fg)

Set the foreground color.

#### **Parameters**

fg [str or tuple of float] color name or tuple of floats, between 0 and 1, inclusive.

# set\_image (image, add\_to\_canvas=True)

Set an image to be displayed.

If there is no error, the 'image-unset' and 'image-set' callbacks will be invoked.

#### Parameters

image [AstroImage or RGBImage] 2D Image object.

add\_to\_canvas [bool] Add image to canvas.

# set\_imap(im)

Set intensity map. See ginga.RGBMap.RGBMapper.set\_imap().

#### set\_intensity\_map(imap\_name)

Set the intensity map.

Available intensity map names can be discovered using ginga.imap.get\_names().

#### **Parameters**

**imap\_name** [str] The name of an intensity map.

#### set\_limits (limits, coord='data')

Set the bounding box of the viewer extents.

#### **Parameters**

**limits** [tuple or None] A tuple setting the extents of the viewer in the form of (ll\_pt, ur\_pt).

set\_name(name)

Set viewer name.

set\_onscreen\_message(text, redraw=True)

Called by a subclass to update the onscreen message.

# Parameters

**text** [str] The text to show in the display.

set\_pan (pan\_x, pan\_y, coord='data', no\_reset=False)
Set pan position.

#### **Parameters**

pan\_x, pan\_y [float] Pan positions in X and Y.

coord [{'data', 'wcs'}] Indicates whether the given pan positions are in data or WCS space.

no\_reset [bool] Do not reset autocenter setting.

#### set\_redraw\_lag(lag\_sec)

Set lag time for redrawing the canvas.

# Parameters

lag\_sec [float] Number of seconds to wait.

#### set\_refresh\_rate(fps)

Set the refresh rate for redrawing the canvas at a timed interval.

#### **Parameters**

fps [float] Desired rate in frames per second.

```
set_renderer (renderer)
```

Set and initialize the renderer used by this instance.

set\_rgbmap(rgbmap)

Set RGB map object used by this instance. It controls how the values in the image are mapped to color.

#### **Parameters**

rgbmap [RGBMapper] RGB map.

# set\_scale(scale, no\_reset=False)

Scale the image in a channel. Also see *zoom\_to()*.

#### **Parameters**

scale [tuple of float] Scaling factors for the image in the X and Y axes.

no\_reset [bool] Do not reset autozoom setting.

set\_scale\_base\_xy (scale\_x\_base, scale\_y\_base)

# Set stretch factors.

#### Parameters

scale\_x\_base, scale\_y\_base [float] Stretch factors for X and Y, respectively.

set\_scale\_limits (scale\_min, scale\_max)

Set scale limits.

#### **Parameters**

scale\_min, scale\_max [float] Minimum and maximum scale limits, respectively.

# set\_window\_size(width, height)

Report the size of the window to display the image.

#### Callbacks

Will call any callbacks registered for the 'configure' event. Callbacks should have a method signature of:

```
(viewer, width, height, ...)
```

Note: This is called by the subclass with width and height as soon as the actual dimensions of the allocated window are known.

#### **Parameters**

width [int] The width of the window in pixels.

height [int] The height of the window in pixels.

set\_zoom\_algorithm(name)

Set zoom algorithm.

**Parameters** 

name [str] Name of a zoom algorithm to use.

set\_zoomrate(zoomrate)

Set zoom rate.

#### **Parameters**

zoomrate [float] Zoom rate.

shift\_cmap(pct)
Shift color map. See ginga.RGBMap.RGBMapper.shift().

show\_color\_bar (tf, side='bottom')

show\_focus\_indicator (tf, color='white')

show\_mode\_indicator(tf, corner='ur')

show\_pan\_mark (tf, color='red')

#### start\_refresh()

Start redrawing the canvas at the previously set timed interval.

#### stop\_refresh()

Stop redrawing the canvas at the previously set timed interval.

#### switch\_cursor(cname)

Switch the viewer's cursor to the one defined under a name.

#### **Parameters**

cname [str] name of the cursor to switch to.

#### take\_focus()

Have the widget associated with this viewer take the keyboard focus. This should be implemented by subclasses, if they have a widget that can take focus.

**transform** (*flip\_x*, *flip\_y*, *swap\_xy*) Transform view of the image.

**Note:** Transforming the image is generally faster than rotating, if rotating in 90 degree increments. Also see *rotate()*.

#### **Parameters**

flipx, flipy [bool] If True, flip the image in the X and Y axes, respectively

swapxy [bool] If True, swap the X and Y axes.

```
transform_cb(setting, value)
```

Handle callback related to changes in transformations.

#### update\_image()

```
update_widget()
```

Update the area corresponding to the backend widget. This must be implemented by subclasses.

classmethod viewable(dataobj)

Test whether dataobj is viewable by this viewer.

window\_has\_origin\_upper()

Indicate if window of backend toolkit is implemented with an origin up or down.

Returns

res [bool] Returns True if the origin is up, False otherwise.

```
window_to_offset (win_x, win_y)
Reverse of offset to window().
```

zoom\_fit (no\_reset=False)

Zoom to fit display window. Also see *zoom\_to()*.

Parameters

no\_reset [bool] Do not reset autozoom setting.

zoom\_in (incr=1.0)
Zoom in a level. Also see zoom\_to().

# Parameters

incr [float (optional, defaults to 1)] The value to increase the zoom level

```
zoom_out (decr=1.0)
Zoom out a level. Also see zoom_to().
```

# Parameters

decr [float (optional, defaults to 1)] The value to decrease the zoom level

zoom\_to(zoomlevel, no\_reset=False)

Set zoom level in a channel. This only changes the relevant settings; The image is not modified. Also see *scale\_to()*.

Note: In addition to the given zoom level, other zoom settings are defined for the channel in preferences.

# Parameters

**zoomlevel** [int] The zoom level to zoom the image. Negative value to zoom out; positive to zoom in.

no\_reset [bool] Do not reset autozoom setting.

zoomsetting\_change\_cb(setting, value)

Handle callback related to changes in zoom.

# 8.8 ginga.rv.main Module

This module handles the main reference viewer.

# 8.8.1 Classes

ReferenceViewer([layout, plugins])	This class exists solely to be able to customize the ref-
	erence viewer startup.

# ReferenceViewer

<pre>class ginga.rv.main.ReferenceViewer</pre>	<pre>(layout=['seq', [], ['vbox', ['name': 'top', 'width': 1400,</pre>	
	rors [G]', 'ptype': 'global'}, {'module': 'Downloads',	
	nets [G], category: Analysis, pipe: global }, {mod- ule': 'Blink', 'workspace': 'dialogs', 'menu': 'Blink Im- ages', 'category': 'Analysis', 'ptype': 'local'}, {'mod- ule': 'Cuts', 'workspace': 'dialogs', 'category': 'Analysis', 'ptype': 'local'}, {'module': 'LineProfile', 'workspace': 'dialogs', 'category': 'Analysis.Datacube', 'ptype': 'lo- cal'}, {'module': 'Histogram', 'workspace': 'dialogs', 'cat-	
8.8. ginga.rv.main Module	cal ], { module : Histogram , workspace : alalogs , cal- egory': 'Analysis', 'ptype': 'local'}, {'module': 'Overlays', 'workspace': 'dialogs', 'category': 'Analysis', 'ptype': 'lo- cal'}, {'module': 'Pick', 'workspace': 'dialogs', 'cate- gory': 'Analysis', 'ptype': 'local'}, {'module': 'PixTable',	227

This class exists solely to be able to customize the reference viewer startup.

# **Methods Summary**

add_default_options(argprs)	Adds the default reference viewer startup options to
	an ArgumentParser instance argprs.
<pre>add_default_plugins([except_global,])</pre>	Add the ginga-distributed default set of plugins to the
	reference viewer.
add_global_plugin(module_name,	
ws_name[,])	
add_global_plugin_spec(spec)	
add_local_plugin(module_name, ws_name[,	
])	
add_local_plugin_spec(spec)	
add_plugin_spec(spec)	
<pre>add_separately_distributed_plugins()</pre>	
clear_default_plugins()	
<pre>main(options, args)</pre>	Main routine for running the reference viewer.

# **Methods Documentation**

add\_default\_options(argprs)

Adds the default reference viewer startup options to an ArgumentParser instance argprs.

- add\_default\_plugins (except\_global=[], except\_local=[])
  Add the ginga-distributed default set of plugins to the reference viewer.
- **add\_global\_plugin** (module\_name, ws\_name, path=None, klass=None, category='Global', tab\_name=None, start\_plugin=True, pfx=None)

add\_global\_plugin\_spec(spec)

add\_local\_plugin (module\_name, ws\_name, path=None, klass=None, pfx=None, category=None)

add\_local\_plugin\_spec(spec)

add\_plugin\_spec(spec)

# add\_separately\_distributed\_plugins()

clear\_default\_plugins()

main (options, args)

Main routine for running the reference viewer.

options is a OptionParser object that has been populated with values from parsing the command line. It should at least include the options from add\_default\_options()

args is a list of arguments to the viewer after parsing out options. It should contain a list of files or URLs to load.

# 8.9 ginga.util.io.io\_asdf Module

Module wrapper for loading ASDF files.

Note: The API for this module is currently unstable and may change in a future release.

# 8.9.1 Functions

<pre>load_file(filepath[, idx, logger])</pre>	Load an object from an ASDF file.
<pre>load_asdf(asdf_obj[, idx, logger])</pre>	Load data from an open ASDF object.
<pre>load_from_asdf(asdf_obj[, data_key,])</pre>	Load from an ASDF object.

# load\_file

ginga.util.io.io\_asdf.load\_file (filepath, idx=None, logger=None, \*\*kwargs)
Load an object from an ASDF file. See ginga.util.loader() for more info.

# load\_asdf

ginga.util.io.io\_asdf.load\_asdf (asdf\_obj, idx=None, logger=None)
Load data from an open ASDF object.

#### **Parameters**

asdf\_obj [obj] ASDF or ASDF-in-FITS object.

idx [None] Currently unused. Reserved for future use to identify specific data set of an ASDF object containing the data of interest.

logger [python logging object] Currently unused. Reserved for future use in logging

#### Returns

data [ndarray or None] Image data, if found.

wcs [obj or None] GWCS object or models, if found.

**ahdr** [dict] Header containing metadata.

# load\_from\_asdf

Load from an ASDF object. This method is primarily used internally to extract the correct parts of an ASDF file to reconstruct an image with WCS and metadata.

#### Parameters

asdf\_obj [obj] ASDF or ASDF-in-FITS object.

data\_key, wcs\_key, header\_key [str] Key values to specify where to find data, WCS, and header in ASDF.

#### Returns

data [ndarray or None] Image data, if found.

wcs [obj or None] GWCS object or models, if found.

ahdr [dict] Header containing metadata.

# 8.9.2 Classes

ASDFFileHandler(logger)

# **ASDFFileHandler**

```
class ginga.util.io.io_asdf.ASDFFileHandler(logger)
    Bases: ginga.util.io.io_base.BaseIOHandler
```

# **Attributes Summary**

#### name

# **Methods Summary**

close()		
<pre>load_asdf(asdf_f[, idx])</pre>		
load_asdf_hdu_in_fits(fits_f,	hdu,	* This is a special method that should only be
**kwargs)		called from WITHIN io_fits.py to open up ASDF-
		embedded-in-FITS *
<pre>load_file(filepath[, idx])</pre>		Load a single data object from a file.
<pre>load_idx(idx, **kwargs)</pre>		
		Parameters
<pre>load_idx_cont(idx_spec, loader_cont)</pre>	ont_fn,	
**kwargs)		Parameters
open_file(filepath, **kwargs)		

# **Attributes Documentation**

name = 'asdf'

# **Methods Documentation**

#### close()

load\_asdf (asdf\_f, idx=None, \*\*kwargs)

#### load\_asdf\_hdu\_in\_fits (fits\_f, hdu, \*\*kwargs)

\* This is a special method that should only be called from WITHIN io\_fits.py to open up ASDFembedded-in-FITS \*

load\_file (filepath, idx=None, \*\*kwargs)

Load a single data object from a file.

#### **Parameters**

- idx [:py:Object] A Python value that matches describes the path or index to a single data data object in the file
- **kwargs** [optional keyword arguments] Any optional keyword arguments are passed to the code that loads the data from the file

#### Returns

data\_obj [subclass of ViewerObjectBase] A supported data wrapper object for a Ginga
viewer

load\_idx (idx, \*\*kwargs)

#### Parameters

- idx [:py:class:object or None] A Python value that matches describes the path or index to a single data data object in the file. Can be None to indicate opening the default (or first usable) object. Acceptable formats are defined by the subclass.
- **kwargs** [optional keyword arguments] Any optional keyword arguments are passed to the code that loads the data from the file

#### Returns

data\_obj [subclass of ViewerObjectBase] A supported data wrapper object for a Ginga
viewer

#### load\_idx\_cont (idx\_spec, loader\_cont\_fn, \*\*kwargs)

#### Parameters

- idx\_spec [str] A string in the form of a pair of brackets enclosing some index expression matching data objects in the file
- **loader\_cont\_fn** [func (data\_obj) -> None] A loader continuation function that takes a data object generated from loading an HDU and does something with it
- **kwargs** [optional keyword arguments] Any optional keyword arguments are passed to the code that loads the data from the file

#### open\_file (filepath, \*\*kwargs)

# 8.9.3 Class Inheritance Diagram



# 8.10 ginga.util.wcsmod Package

We are fortunate to have several possible choices for a python WCS package compatible with Ginga: astlib, kapteyn, starlink and astropy. kapteyn and astropy wrap Mark Calabretta's "WCSLIB", astLib wraps Jessica Mink's "wcstools", and I'm not sure what starlink uses (their own?).

Note that astlib requires pyfits (or astropy) in order to create a WCS object from a FITS header.

To force the use of one, do:

from ginga.util import wcsmod
wcsmod.use('kapteyn')

before you load any images. Otherwise Ginga will try to pick one for you.

Note that you can register custom WCS types using:

```
from ginga.util.wcsmod.common import register_wcs
register_wcs('mywcs', MyWCSClass, list_of_coord_types)
```

Look at the implemented WCS wrappers for details.

# 8.10.1 Functions

get_wcs_class(name)	Get a WCS class corresponding to the registered name.

# get\_wcs\_class

ginga.util.wcsmod.get\_wcs\_class(name)

Get a WCS class corresponding to the registered name. Will raise a KeyError if a class of the given name does not exist.

# 8.11 ginga.util.wcs Module

This module handles calculations based on world coordinate system.

# 8.11.1 Functions

hmsToDeg(h, m, s)	Convert RA hours, minutes, seconds into an angle in degrees.
dmsToDeg(sign, deg, min, sec)	Convert dec sign, degrees, minutes, seconds into a signed angle in degrees.
decTimeToDeg(sign_sym, deg, min, sec)	Convert dec sign, degrees, minutes, seconds into a signed angle in degrees.
degToHms(ra)	Converts the ra (in degrees) to HMS three tuple.
<pre>degToDms(dec[, isLatitude])</pre>	Convert the dec, in degrees, to an (sign,D,M,S) tuple.
arcsecToDeg(arcsec)	Convert numeric arcseconds (aka DMS seconds) to de- grees of arc.
hmsStrToDeg(ra)	Convert a string representation of RA into a float in de- grees.
dmsStrToDeg(dec)	Convert a string representation of DEC into a float in degrees.
<pre>raDegToString(ra_deg[, format])</pre>	
<pre>decDegToString(dec_deg[, format])</pre>	
<pre>trans_coeff(eq, x, y, z)</pre>	This function is provided by MOKA2 Development Team (1996.xx.xx) and used in SOSS system.
eqToEq2000(ra_deg, dec_deg, eq)	Convert Eq to Eq 2000.
<pre>get_xy_rotation_and_scale(header)</pre>	CREDIT: See IDL code at http://www.astro. washington.edu/docs/idl/cgi-bin/getpro/library32. html?GETROT
<pre>get_rotation_and_scale(header[, skew_threshold])</pre>	Calculate rotation and CDELT.
<pre>get_relative_orientation(image, ref_image)</pre>	Computes the relative orientation and scale of an image to a reference image.
<pre>simple_wcs(px_x, px_y, ra_deg, dec_deg,)</pre>	Calculate a set of WCS keywords for a 2D simple in- strument FITS file with a 'standard' RA/DEC pixel pro- jection.
<pre>deg2fmt(ra_deg, dec_deg, format)</pre>	Format coordinates.
dispos(dra0, decd0, dra, decd)	Compute distance and position angle solving a spherical triangle (no approximations).
<pre>deltaStarsRaDecDeg1(ra1_deg, dec1_deg,)</pre>	Spherical triangulation.
<pre>deltaStarsRaDecDeg2(ral_deg, decl_deg,)</pre>	-
<pre>get_starsep_RaDecDeg(ra1_deg, dec1_deg,)</pre>	Calculate separation.
add_offset_radec(ra_deg, dec_deg,)	Algorithm to compute RA/Dec from RA/Dec base posi- tion plus tangent plane offsets.
<pre>get_RaDecOffsets(ral_deg, decl_deg, ra2_deg,)</pre>	Calculate offset.
lon_to_deg(lon)	Convert longitude to degrees.
lat_to_deg(lat)	Convert latitude to degrees.
<u> </u>	

### hmsToDeg

ginga.util.wcs.hmsToDeg(h, m, s)
Convert RA hours, minutes, seconds into an angle in degrees.

#### dmsToDeg

ginga.util.wcs.dmsToDeg(sign, deg, min, sec)
Convert dec sign, degrees, minutes, seconds into a signed angle in degrees.

# decTimeToDeg

ginga.util.wcs.decTimeToDeg (sign\_sym, deg, min, sec)
Convert dec sign, degrees, minutes, seconds into a signed angle in degrees.

sign\_sym may represent negative as either '-' or numeric -1.

#### degToHms

ginga.util.wcs.**degToHms** (*ra*) Converts the ra (in degrees) to HMS three tuple. H and M are in integer and the S part is in float.

# degToDms

ginga.util.wcs.**degToDms** (*dec*, *isLatitude=True*) Convert the dec, in degrees, to an (sign,D,M,S) tuple. D and M are integer, and sign and S are float.

#### arcsecToDeg

ginga.util.wcs.arcsecToDeg(arcsec)
Convert numeric arcseconds (aka DMS seconds) to degrees of arc.

# hmsStrToDeg

ginga.util.wcs.hmsStrToDeg(*ra*) Convert a string representation of RA into a float in degrees.

### dmsStrToDeg

ginga.util.wcs.dmsStrToDeg(dec)
Convert a string representation of DEC into a float in degrees.

# raDegToString

ginga.util.wcs.raDegToString(ra\_deg, format='%02d:%02d:%06.3f')

# decDegToString

ginga.util.wcs.decDegToString(dec\_deg,format='%s%02d:%02d:%05.2f')

# trans\_coeff

ginga.util.wcs.**trans\_coeff** (*eq*, *x*, *y*, *z*) This function is provided by MOKA2 Development Team (1996.xx.xx) and used in SOSS system.

# eqToEq2000

ginga.util.wcs.eqToEq2000(ra\_deg, dec\_deg, eq)
Convert Eq to Eq 2000.

### get\_xy\_rotation\_and\_scale

#### get\_rotation\_and\_scale

ginga.util.wcs.get\_rotation\_and\_scale (*header*, *skew\_threshold=0.001*) Calculate rotation and CDELT.

### get\_relative\_orientation

ginga.util.wcs.get\_relative\_orientation (image, ref\_image)
Computes the relative orientation and scale of an image to a reference image.

#### Parameters

image AstroImage based object

ref\_image AstroImage based object

#### Returns

result Bunch object containing the relative scale in x and y and the relative rotation in degrees.

# simple\_wcs

ginga.util.wcs.simple\_wcs(px\_x, px\_y, ra\_deg, dec\_deg, px\_scale\_deg\_px, rot\_deg, cdbase=[1, 1])
Calculate a set of WCS keywords for a 2D simple instrument FITS file with a 'standard' RA/DEC pixel projection.

#### **Parameters**

**px\_x** (ZERO-based) reference pixel of field in X (usually center of field)

px\_y (ZERO-based) reference pixel of field in Y (usually center of field)

ra\_deg RA (in deg) for the reference point

dec\_deg DEC (in deg) for the reference point

**px\_scale\_deg\_px** Pixel scale (deg/pixel); can be a tuple for different x,y scales

rot\_deg Rotation angle of the field (in deg)

cdbase CD base

#### Returns

res [dict] Ordered dictionary object containing WCS headers.

#### deg2fmt

ginga.util.wcs.deg2fmt (ra\_deg, dec\_deg, format)
Format coordinates.

# dispos

ginga.util.wcs.**dispos** (*dra0*, *decd0*, *dra*, *decd*) Compute distance and position angle solving a spherical triangle (no approximations).

Source/credit: Skycat Author: A.P. Martinez

#### Parameters

dra0 [float] Center RA in decimal degrees.

**decd0** [float] Center DEC in decimal degrees.

dra [float] Point RA in decimal degrees.

decd [float] Point DEC in decimal degrees.

#### Returns

phi [float] Phi in degrees (East of North).

dist [float] Distance in arcmin.

# deltaStarsRaDecDeg1

ginga.util.wcs.deltaStarsRaDecDeg1(ral\_deg, decl\_deg, ra2\_deg, dec2\_deg)
 Spherical triangulation.

# deltaStarsRaDecDeg2

ginga.util.wcs.deltaStarsRaDecDeg2(ra1\_deg, dec1\_deg, ra2\_deg, dec2\_deg)

# get\_starsep\_RaDecDeg

ginga.util.wcs.get\_starsep\_RaDecDeg(ral\_deg, decl\_deg, ra2\_deg, dec2\_deg)
Calculate separation.

# add\_offset\_radec

ginga.util.wcs.**add\_offset\_radec**(*ra\_deg*, *dec\_deg*, *delta\_deg\_ra*, *delta\_deg\_dec*) Algorithm to compute RA/Dec from RA/Dec base position plus tangent plane offsets.

# get\_RaDecOffsets

ginga.util.wcs.get\_RaDecOffsets(ral\_deg, decl\_deg, ra2\_deg, dec2\_deg)
Calculate offset.

# lon\_to\_deg

ginga.util.wcs.lon\_to\_deg(lon)
Convert longitude to degrees.

# lat\_to\_deg

ginga.util.wcs.lat\_to\_deg(lat)
Convert latitude to degrees.

# 8.12 ginga.util.ap\_region Module

This module provides Ginga support for DS9 type region files and objects via the Astropy regions module.

# 8.12.1 Functions

<pre>astropy_region_to_ginga_canvas_objec</pre>	$ct(\mathbf{r})$ Convert an Astropy region object to a Ginga canvas ob-
ject.	
add_region(canvas, r[, tag, redraw])	Convenience function to plot an Astropy regions object
	on a Ginga canvas.
ginga_canvas_object_to_astropy_regio	on(obf) onvert a Ginga canvas object to an AstroPy region ob-
	ject.

# astropy\_region\_to\_ginga\_canvas\_object

ginga.util.ap\_region.astropy\_region\_to\_ginga\_canvas\_object(r) Convert an Astropy region object to a Ginga canvas object.

### Parameters

 ${f r}$  [subclass of PixelRegion] The region object to be converted

### Returns

obj [subclass of CanvasObject] The corresponding Ginga canvas object

# add\_region

```
ginga.util.ap_region.add_region(canvas, r, tag=None, redraw=True)
Convenience function to plot an Astropy regions object on a Ginga canvas.
```

#### **Parameters**

canvas [DrawingCanvas] The Ginga canvas on which the region should be plotted.

- r [subclass of PixelRegion] The region object to be plotted
- tag [str or None (optional, default: None)] Caller can optionally pass a specific tag for the canvas object
- **redraw** [bool (optional, default: True)] True if the viewers of the canvas should be updated immediately

# ginga\_canvas\_object\_to\_astropy\_region

```
ginga.util.ap_region.ginga_canvas_object_to_astropy_region (obj)
Convert a Ginga canvas object to an AstroPy region object.
```

#### Parameters

obj [subclass of CanvasObject] The Ginga canvas object to be converted

# Returns

r [subclass of <code>PixelRegion</code>] The corresponding AstroPy region object

Some training videos are available in the downloads page on Github.

Be sure to also check out the Ginga wiki.

# Part VII

# **Bug Reports**

Please file an issue with the issue tracker on Github.

Ginga has a logging facility, and it would be most helpful if you can invoke Ginga with the logging options to capture any logged errors:

ginga --loglevel=20 --log=ginga.log

If the difficulty is with non-display or non-working World Coordinate System (WCS) for a particular image file please be ready to supply the file for our aid in debugging.

# Part VIII

# **Developer Info**

In the source code examples/\* directories, see example {1,2}\_gtk.py (Gtk), example {1,2}\_qt.py (Qt), example {1,2}\_tk.py (Tk), or example {1,2,3,4,5}\_mpl.py (Matplotlib). There is more information for developers in the *Developer's Manual*.

See also the *Reference/API* or Module Index for a list of the available modules.

# Part IX

# Etymology

"Ginga" is the romanized spelling of the Japanese word "NN" (Hiragana: NNN), meaning "galaxy" (in general) and, more familiarly, the Milky Way. This viewer was written by software engineers at Subaru Telescope, National Astronomical Observatory of Japan, thus the connection.

# Part X

# Pronunciation

Ginga the viewer may be pronounced "ging-ga" (proper Japanese) or "jing-ga" (perhaps easier for Westerners). The latter pronunciation has meaning in the Brazilian dance/martial art Capoeira: a fundamental rocking or back and forth swinging motion. Pronunciation as "jin-ja" is considered poor form.

### **PYTHON MODULE INDEX**

### С

ginga.canvas.CanvasMixin, 183 ginga.canvas.CanvasObject, 185 ginga.canvas.CompoundMixin, 189 ginga.canvas.coordmap, 192 ginga.canvas.DrawingMixin, 197 ginga.canvas.types.layer, 200

### i

ginga.ImageView,201

### r

```
ginga.rv.main, 226
ginga.rv.plugins.Blink,107
ginga.rv.plugins.Catalogs, 116
ginga.rv.plugins.ChangeHistory, 79
ginga.rv.plugins.Collage, 118
ginga.rv.plugins.Colorbar,69
ginga.rv.plugins.ColorMapPicker,72
ginga.rv.plugins.Command,82
ginga.rv.plugins.Compose, 120
ginga.rv.plugins.Contents,68
ginga.rv.plugins.Crosshair,100
ginga.rv.plugins.Cursor,70
ginga.rv.plugins.Cuts,97
ginga.rv.plugins.Downloads,84
ginga.rv.plugins.Drawing, 119
ginga.rv.plugins.Errors,73
ginga.rv.plugins.FBrowser, 120
ginga.rv.plugins.Header, 64
ginga.rv.plugins.Histogram,98
ginga.rv.plugins.Info,63
ginga.rv.plugins.LineProfile, 108
ginga.rv.plugins.Log,81
ginga.rv.plugins.Mosaic, 117
ginga.rv.plugins.MultiDim,96
ginga.rv.plugins.Operations,70
ginga.rv.plugins.Overlays, 102
ginga.rv.plugins.Pan, 62
ginga.rv.plugins.Pick,85
ginga.rv.plugins.Pipeline, 124
ginga.rv.plugins.PixTable, 109
```

ginga.rv.plugins.PlotTable, 123
ginga.rv.plugins.Preferences, 111
ginga.rv.plugins.RC, 73
ginga.rv.plugins.Ruler, 94
ginga.rv.plugins.SAMP, 80
ginga.rv.plugins.SaveImage, 83
ginga.rv.plugins.ScreenShot, 124
ginga.rv.plugins.Thumbs, 67
ginga.rv.plugins.Toolbar, 61
ginga.rv.plugins.TVMark, 104
ginga.rv.plugins.WBrowser, 70
ginga.rv.plugins.WCSAxes, 103
ginga.rv.plugins.WCSMatch, 77
ginga.rv.plugins.Zoom, 65

### u

ginga.util.ap\_region, 237
ginga.util.io.io\_asdf, 229
ginga.util.wcs, 233
ginga.util.wcsmod, 232

## INDEX

A	230
add() (ginga.canvas.CanvasMixin.CanvasMixin method), 184	<pre>astropy_region_to_ginga_canvas_object()     (in module ginga.util.ap_region), 238</pre>
<pre>add_default_options()     (ginga.rv.main.ReferenceViewer method),     228</pre>	<pre>auto_levels() (ginga.ImageView.ImageViewBase</pre>
add_default_plugins()	<i>method</i> ), 207
(ginga.rv.main.ReferenceViewer method), 228	<pre>auto_orient() (ginga.ImageView.ImageViewBase method), 207</pre>
<pre>add_draw_mode() (ginga.canvas.DrawingMixin.Draw method), 198</pre>	C
<pre>add_global_plugin()     (ginga.rv.main.ReferenceViewer method),     228</pre>	<pre>calc_dual_scale_from_pt()     (ginga.canvas.CanvasObject.CanvasObjectBase     method), 187</pre>
<pre>add_global_plugin_spec()     (ginga.rv.main.ReferenceViewer method),     228</pre>	<pre>calc_offsets() (ginga.canvas.coordmap.OffsetMapper</pre>
<pre>add_local_plugin()     (ginga.rv.main.ReferenceViewer method),     228</pre>	<pre>method), 187 calc_rotation_from_pt()     (ginga.canvas.CanvasObject.CanvasObjectBase</pre>
<pre>add_local_plugin_spec()     (ginga.rv.main.ReferenceViewer method),     228</pre>	<pre>method), 187 calc_scale_from_pt()     (ginga.canvas.CanvasObject.CanvasObjectBase</pre>
<pre>add_object() (ginga.canvas.CompoundMixin.Compou method), 191</pre>	
<pre>add_offset_radec() (in module ginga.util.wcs),</pre>	method), 187 Canvas (class in ginga.canvas.types.layer), 200
<pre>add_plugin_spec()     (ginga.rv.main.ReferenceViewer method),     228</pre>	canvas_changed_cb() ( <i>ginga.ImageView.ImageViewBase method</i> ), 207
<pre>add_region() (in module ginga.util.ap_region), 238 add_separately_distributed_plugins()         (ginga.rv.main.ReferenceViewer method), 228</pre>	<pre>canvascoords() (ginga.canvas.CanvasObject.CanvasObjectBase method), 187 canvascoords() (ginga.ImageView.ImageViewBase</pre>
<pre>addObject() (ginga.canvas.CompoundMixin.Compour method), 191</pre>	CanvasMixin ( <i>class in ginga.canvas.CanvasMixin</i> ),
<pre>apply_profile() (ginga.ImageView.ImageViewBase</pre>	183 CanvasObjectBase (class in
<pre>apply_profile_or_settings()     (ginga.ImageView.ImageViewBase method),     207</pre>	<pre>ginga.canvas.CanvasObject), 185 capture_profile()   (ginga.ImageView.ImageViewBase method),</pre>
<pre>arcsecToDeg() (in module ginga.util.wcs), 234 ASDFFileHandler (class in ginga.util.io.io_asdf),</pre>	208 CartesianMapper ( <i>class in ginga.canvas.coordmap</i> ),

194	<pre>data_to() (ginga.canvas.coordmap.DataMapper</pre>
center_cursor() (ginga.ImageView.ImageViewBase	<i>method</i> ), 195
method), 208	data_to() (ginga.canvas.coordmap.NativeMapper
center_image() (ginga.ImageView.ImageViewBase	method), 193
method), 208	data_to() (ginga.canvas.coordmap.OffsetMapper
check_cursor_location()	method), 196
(ginga.ImageView.ImageViewBase method), 208	data_to() (ginga.canvas.coordmap.PercentageMapper
checkpoint_profile()	<pre>method), 194 data_to() (ginga.canvas.coordmap.WCSMapper</pre>
(ginga.ImageView.ImageViewBase method),	<pre>data_to() (ginga.canvas.coordmap.WCSMapper method), 197</pre>
208	data_to() (ginga.canvas.coordmap.WindowMapper
<pre>clear() (ginga.ImageView.ImageViewBase method),</pre>	method), 193
208	data_to_offset() (ginga.ImageView.ImageViewBase
clear_default_plugins()	method), 208
(ginga.rv.main.ReferenceViewer method),	DataMapper ( <i>class in ginga.canvas.coordmap</i> ), 195
228	decDegToString() (in module ginga.util.wcs), 235
<pre>clear_selected() (ginga.canvas.DrawingMixin.Dra</pre>	
<i>method</i> ), 198	define_cursor() (ginga.ImageView.ImageViewBase
close() (ginga.util.io.io_asdf.ASDFFileHandler	method), 209
<i>method</i> ), 231	deg2fmt() (in module ginga.util.wcs), 236
CompoundMixin (class in	degToDms() (in module ginga.util.wcs), 234
ginga.canvas.CompoundMixin), 190	degToHms() (in module ginga.util.wcs), 234
CompoundObject (class in ginga.canvas.types.layer),	<pre>delayed_redraw() (ginga.ImageView.ImageViewBase</pre>
200	<i>method</i> ), 209
<pre>configure() (ginga.ImageView.ImageViewBase</pre>	<pre>delete_all_objects()</pre>
<i>method</i> ), 208	(ginga.canvas.CanvasMixin.CanvasMixin
<pre>configure_surface()</pre>	<i>method</i> ), 184
(ginga.ImageView.ImageViewBase method),	-
208	(ginga. canvas. Compound Mixin. Compound Mixin
contains() (ginga.canvas.CanvasObject.CanvasObject	
<i>method</i> ), 187	<pre>delete_object() (ginga.canvas.CanvasMixin.CanvasMixin</pre>
contains_arr() (ginga.canvas.CanvasObject.Canvas	
method), 187	delete_object()(ginga.canvas.CompoundMixin.CompoundMixin
contains_pt() (ginga.canvas.CanvasObject.CanvasO	
method), 187	delete_object_by_tag() ObjectProc(since server Minin Comme Minin
contains_pts() (ginga.canvas.CanvasObject.Canvas	
method), 187	method), 184 palardl <b>Mixin</b> objects() (ginga.canvas.CanvasMixin.CanvasMixin
	method), 184
method), 191	pasi@bjectBasecjects() (ginga.canvas.CompoundMixin.CompoundMixin
method), 187	method), 191
copy_attributes()	delete_objects_by_tag()
(ginga.ImageView.ImageViewBase method),	(ginga.canvas.CanvasMixin.CanvasMixin
208	method), 184
copy_to_dst() (ginga.ImageView.ImageViewBase	deleteAllObjects()
<i>method</i> ), 208	(ginga.canvas.CanvasMixin.CanvasMixin
<pre>cut_levels() (ginga.ImageView.ImageViewBase</pre>	<i>method</i> ), 184
<i>method</i> ), 208	deleteAllObjects()
<pre>cut_levels_cb() (ginga.ImageView.ImageViewBase</pre>	(ginga.canvas.CompoundMixin.CompoundMixin
<i>method</i> ), 208	method), 191
D	<pre>deleteObject() (ginga.canvas.CanvasMixin.CanvasMixin</pre>
D	<i>method</i> ), 184
<pre>data_to() (ginga.canvas.coordmap.CartesianMapper</pre>	<pre>deleteObject() (ginga.canvas.CompoundMixin.CompoundMixin</pre>
<i>method</i> ), 195	<i>method</i> ), 191

<pre>deleteObjectByTag()     (ginga.canvas.CanvasMixin.CanvasMixin</pre>	<pre>method), 199 edit_rotate() (ginga.canvas.DrawingMixin.DrawingMixin</pre>
<pre>method), 184 deleteObjects() (ginga.canvas.CanvasMixin.Canvas</pre>	method), 199 Meidint_scale() (ginga.canvas.DrawingMixin.DrawingMixin
method), 184	method), 199
<pre>deleteObjects() (ginga.canvas.CompoundMixin.Com</pre>	npodiatd <u>Mixilect()</u> (ginga.canvas.DrawingMixin.DrawingMixin method), 199
deleteObjectsByTag()	<pre>edit_start() (ginga.canvas.DrawingMixin.DrawingMixin</pre>
(ginga.canvas.CanvasMixin.CanvasMixin	method), 199
method), 184	<pre>edit_stop() (ginga.canvas.DrawingMixin.DrawingMixin</pre>
deltaStarsRaDecDeg1() (in module ginga.util.wcs), 237	method), 199
deltaStarsRaDecDeg2() (in module	<pre>enable_auto_orient()     (ginga.ImageView.ImageViewBase method),</pre>
ginga.util.wcs), 237	209
dispos () (in module ginga.util.wcs), 236	enable_autocenter()
dmsStrToDeg() (in module ginga.util.wcs), 234	(ginga.ImageView.ImageViewBase method),
dmsToDeg() (in module ginga.util.wcs), 234	209
draw() (ginga.canvas.CompoundMixin.CompoundMixin	enable_autocuts()
<i>method</i> ), 191	(ginga.ImageView.ImageViewBase method),
draw() (ginga.canvas.DrawingMixin.DrawingMixin	209
method), 198	<pre>enable_autozoom()</pre>
<pre>draw_arrowhead() (ginga.canvas.CanvasObject.Canv method), 187</pre>	vasObjectBd, <b>ga</b> inga.ImageView.ImageViewBase method), 209
<pre>draw_caps() (ginga.canvas.CanvasObject.CanvasObje method), 187</pre>	<pre>ctBaseble_draw() (ginga.canvas.DrawingMixin.DrawingMixin method), 199</pre>
	<pre>ctBaseble_edit() (ginga.canvas.DrawingMixin.DrawingMixin method), 199</pre>
draw_motion() (ginga.canvas.DrawingMixin.Drawing	
araw_motion() (ginga.cunvas.Drawingmixin.Drawing	(MHIGHOEQ2000()) (in module ginga.ull.wcs), 255
<i>method</i> ), 198	
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198</pre>	
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()</pre>	ingMixin get_autocenter_options() (ginga.ImageView.ImageViewBase method),
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin</pre>	ing Mixin get_autocenter_options() (ginga.ImageView.ImageViewBase method), 209
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods()</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.D</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.D</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() Mixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw     method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete()     (ginga.canvas.DrawingMixin.DrawingMixin     method), 198 draw_start() (ginga.canvas.DrawingMixin.D</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() Mixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method), </pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox() (ginga.canvas.CanvasObject.CanvasObjectBase     method), 187</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E edit_delete() (ginga.canvas.DrawingMixin.Drawing method), 199</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox()(ginga.canvas.CanvasObject.CanvasObjectBase     method), 187 Misin_bg()(ginga.ImageView.ImageViewBase method),     210</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMix method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E edit_delete() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_delete_cb() (ginga.canvas.DrawingMixin.Drawing method), 199</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox() (ginga.canvas.CanvasObject.CanvasObjectBase     method), 187 Misin_bg() (ginga.ImageView.ImageViewBase method),     210 wingMisin_bg() (ginga.ImageView.ImageViewBase method),     210 wingMisin_nvas() (ginga.ImageView.ImageViewBase method),     210</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMix method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMix method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E edit_delete() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_delete_cb() (ginga.canvas.DrawingMixin.Dra</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox()(ginga.canvas.CanvasObject.CanvasObjectBase     method), 187 Mixin_bg() (ginga.ImageView.ImageViewBase method),     210 wingMixin_bg() (ginga.ImageView.ImageViewBase method),     210 wingMixin_bg() (ginga.ImageView.ImageViewBase method),     210 WingMixin_vas() (ginga.ImageView.ImageViewBase method),     210 WingMixin_canvas_image()</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E edit_delete() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_delete_cb() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_motion() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_poly_add() (ginga.canvas.DrawingMixin.Dra</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox() (ginga.canvas.CanvasObject.CanvasObjectBase     method), 187 Misin_bg() (ginga.ImageView.ImageViewBase method),     210 wingeMisin_nvas() (ginga.ImageView.ImageViewBase method),     210 wingeMisin_canvas() (ginga.ImageView.ImageViewBase method),     210 Misin_canvas_image()     (ginga.ImageView.ImageViewBase method),     110 Misin_canvas_image()     (ginga.ImageView.ImageViewBase method),     ingMixin 210</pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMi method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMi method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E edit_delete() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_delete_cb() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_motion() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_poly_add() (ginga.canvas.DrawingMixin.Draw method), 199</pre>	<pre>ingWixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() Mixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox()(ginga.canvas.CanvasObject.CanvasObjectBase     method),     187 Mixim_bg()(ginga.ImageView.ImageViewBase method),     210 wiyseMixim_vas() (ginga.ImageView.ImageViewBase method),     210 wiyseMixim_vas() (ginga.ImageView.ImageViewBase method),     210 wiyseMixim_vas() (ginga.ImageView.ImageViewBase method),     210 wiyseMixim_vas() (ginga.ImageViewBase method),     210 mixim_canvas_image()     (ginga.ImageView.ImageViewBase method),     ingMixin 210 get_canvas_pt()(ginga.ImageView.ImageViewBase </pre>
<pre>method), 198 draw_poly_add() (ginga.canvas.DrawingMixin.Draw method), 198 draw_poly_delete() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_start() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 draw_stop() (ginga.canvas.DrawingMixin.DrawingMixin method), 198 DrawingCanvas (class in ginga.canvas.types.layer), 201 DrawingMixin (class in ginga.canvas.DrawingMixin), 197 E edit_delete() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_delete_cb() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_motion() (ginga.canvas.DrawingMixin.Drawing method), 199 edit_poly_add() (ginga.canvas.DrawingMixin.Dra</pre>	<pre>ingMixin get_autocenter_options()     (ginga.ImageView.ImageViewBase method),     209 get_autocut_methods() fixin (ginga.ImageView.ImageViewBase method),     209 xiget_autocuts_options()     (ginga.ImageView.ImageViewBase method),     210 get_autozoom_options()     (ginga.ImageView.ImageViewBase method),     210 get_bbox() (ginga.canvas.CanvasObject.CanvasObjectBase     method), 187 Misin_bg() (ginga.ImageView.ImageViewBase method),     210 wingeMisin_nvas() (ginga.ImageView.ImageViewBase method),     210 wingeMisin_canvas() (ginga.ImageView.ImageViewBase method),     210 Misin_canvas_image()     (ginga.ImageView.ImageViewBase method),     110 Misin_canvas_image()     (ginga.ImageView.ImageViewBase method),     ingMixin 210</pre>

<pre>get_canvas_type() (in module</pre>	get_draw_rect()(ginga.ImageView.ImageViewBase
ginga.canvas.CanvasObject), 185	method), 212
get_canvas_types() (in module ginga.canvas.CanvasObject), 185	method), 199
<pre>get_canvas_xy() (ginga.ImageView.ImageViewBase</pre>	<pre>get_drawtype() (ginga.canvas.DrawingMixin.DrawingMixin</pre>
<pre>get_center() (ginga.ImageView.ImageViewBase method), 210</pre>	<pre>get_drawtypes() (ginga.canvas.DrawingMixin.DrawingMixin method), 199</pre>
<pre>get_center_pt() (ginga.canvas.CanvasObject.Canva method), 188</pre>	
get_center_pt() (ginga.canvas.CompoundMixin.Com	
<i>method</i> ), 191	<pre>get_edit_points()</pre>
<pre>get_color_algorithms()         (ginga.ImageView.ImageViewBase method),</pre>	(ginga.canvas.CompoundMixin.CompoundMixin method), 191
(ginga.imageview.imageview.base method), 210	get_fg() (ginga.ImageView.ImageViewBase method),
<pre>get_coordmap() (ginga.ImageView.ImageViewBase</pre>	212
<i>method</i> ), 210	get_image() (ginga.ImageView.ImageViewBase
<pre>get_cpoints() (ginga.canvas.CanvasObject.CanvasO</pre>	
<i>method</i> ), 188	<pre>get_image_as_array()</pre>
<pre>get_cursor() (ginga.ImageView.ImageViewBase</pre>	(ginga.ImageView.ImageViewBase method), 212
<pre>get_cut_levels() (ginga.ImageView.ImageViewBase</pre>	
method), 211	(ginga.ImageView.ImageViewBase method),
<pre>get_data() (ginga.canvas.CanvasObject.CanvasObject method), 188</pre>	Base 212 get_items_at()(ginga.canvas.CompoundMixin.CompoundMixin
get_data() (ginga.ImageView.ImageViewBase	method), 191
method), 211	<pre>get_last_data_xy()</pre>
<pre>get_data_pct() (ginga.ImageView.ImageViewBase</pre>	(ginga.ImageView.ImageViewBase method), 212
<pre>get_data_points()</pre>	<pre>get_last_win_xy()</pre>
(ginga.canvas.CanvasObject.CanvasObjectBase method), 188	(ginga.ImageView.ImageViewBase method), 212
<pre>get_data_pt() (ginga.ImageView.ImageViewBase method), 211</pre>	<pre>get_limits() (ginga.ImageView.ImageViewBase method), 213</pre>
<pre>get_data_size() (ginga.ImageView.ImageViewBase</pre>	
<pre>get_data_xy() (ginga.ImageView.ImageViewBase method), 211</pre>	<pre>get_logger() (ginga.ImageView.ImageViewBase method), 213</pre>
<pre>get_dataobj() (ginga.ImageView.ImageViewBase</pre>	<pre>get_move_scale_rotate_pts()</pre>
<i>method</i> ), 211	(ginga.canvas.CanvasObject.CanvasObjectBase
<pre>get_datarect() (ginga.ImageView.ImageViewBase</pre>	<i>method</i> ), 188
<i>method</i> ), 211	<pre>get_num_points() (ginga.canvas.CanvasObject.CanvasObjectBase</pre>
<pre>get_desired_size()</pre>	method), 188
(ginga.ImageView.ImageViewBase method), 212	get_object_by_tag() (ainag camuas Camuas Mixin Camuas Mixin
get_dims() (ginga.ImageView.ImageViewBase	(ginga.canvas.CanvasMixin.CanvasMixin method), 184
method), 212	get_objects()(ginga.canvas.CompoundMixin.CompoundMixin
get_draw_class() (ginga.canvas.DrawingMixin.Dra	
method), 199	get_objects_by_kind()
<pre>get_draw_classes()</pre>	(ginga.canvas.CompoundMixin.CompoundMixin
(ginga.canvas.DrawingMixin.DrawingMixin	<i>method</i> ), 191
method), 199	get_objects_by_kinds()
<pre>get_draw_mode() (ginga.canvas.DrawingMixin.Draw method), 199</pre>	ingMixin (ginga.canvas.CompoundMixin.CompoundMixin method), 191

get\_objects\_by\_tag\_pfx() (ginga.canvas.CanvasMixin.CanvasMixin method). 184(ginga.ImageView.ImageViewBase get\_pan() method), 213 get pan rect() (ginga.ImageView.ImageViewBase method), 213 get\_params\_metadata() (ginga.canvas.types.layer.Canvas class method), 201 get\_params\_metadata() (ginga.canvas.types.layer.CompoundObject class method), 200 get\_pixel\_distance() (ginga.ImageView.ImageViewBase method), 213 get\_plain\_image\_as\_widget() (ginga.ImageView.ImageViewBase *method*). 213 get\_point\_by\_index() method), 188 get\_points() (ginga.canvas.CanvasObject.CanvasObjectBasescale\_text() (ginga.ImageView.ImageViewBase method), 188 get\_points() (ginga.canvas.CompoundMixin.CompoundMixiBcale\_xy() (ginga.ImageView.ImageViewBase *method*), 191 get\_private\_canvas() (ginga.ImageView.ImageViewBase method), 213get\_pt() (ginga.canvas.CanvasObject.CanvasObjectBase *method*), 188 get\_RaDecOffsets() (in module ginga.util.wcs), 237 get\_reference\_pt() (ginga.canvas.CanvasObject.CanvasObjectBase get\_tags\_by\_tag\_pfx() method), 188 get\_reference\_pt() method), 191 get\_refresh\_stats() (ginga.ImageView.ImageViewBase method), 213get\_relative\_orientation() (in module ginga.util.wcs), 235 get\_rgb\_image\_as\_buffer() (ginga.ImageView.ImageViewBase *method*), 214 get\_rgb\_image\_as\_bytes() (ginga.ImageView.ImageViewBase *method*), 214 get\_rgb\_image\_as\_widget() (ginga.ImageView.ImageViewBase method), 214 get rgb order() (ginga.ImageView.ImageViewBase get zoomrate() (ginga.ImageView.ImageViewBase

method), 214 (ginga.ImageView.ImageViewBase get\_rgbmap() method), 214 get\_rotation() (ginga.ImageView.ImageViewBase method), 214 get rotation and scale() (in module ginga.util.wcs), 235 get\_rotation\_info() (ginga.ImageView.ImageViewBase method), 215 (ginga.ImageView.ImageViewBase get\_scale() method), 215 get\_scale\_base\_xy() (ginga.ImageView.ImageViewBase *method*), 215 get\_scale\_limits() (ginga.ImageView.ImageViewBase method), 215 get\_scale\_max() (ginga.ImageView.ImageViewBase method), 215 (ginga.canvas.CanvasObject.CanvasObjectBase get\_scale\_min() (ginga.ImageView.ImageViewBase method), 215 method), 215 method), 215 get\_selected() (ginga.canvas.DrawingMixin.DrawingMixin method), 199 get\_settings() (ginga.ImageView.ImageViewBase method), 215 get\_starsep\_RaDecDeg() (in module ginga.util.wcs), 237 get\_tags() (ginga.canvas.CanvasMixin.CanvasMixin method), 184 (ginga.canvas.CanvasMixin.CanvasMixin method), 184 (ginga.canvas.CompoundMixin.CompoundMixin get\_transforms() (ginga.ImageView.ImageViewBase method), 215 (ginga.ImageView.ImageViewBase get\_vip() method), 216 get\_wcs\_class() (in module ginga.util.wcsmod), 232 get\_window\_size() (ginga.ImageView.ImageViewBase method), 216 get\_xy\_rotation\_and\_scale() (in module ginga.util.wcs), 235 get\_zoom() (ginga.ImageView.ImageViewBase method), 216 get\_zoom\_algorithm() (ginga.ImageView.ImageViewBase *method*), 216

method), 216 module, 100 getDrawClass() (ginga.canvas.DrawingMixin.DrawingMixinga.rv.plugins.Cursor method), 199 module, 70 getItemsAt()(ginga.canvas.CompoundMixin.CompoundMixia.rv.plugins.Cuts *method*), 191 module, 97 getObjectByTag() (ginga.canvas.CanvasMixin.CanvasMixinga.rv.plugins.Downloads method), 184 module.84 getObjects()(ginga.canvas.CompoundMixin.CompoundMixia.rv.plugins.Drawing method), 191 module, 119 getObjectsByTagpfx() ginga.rv.plugins.Errors (ginga.canvas.CanvasMixin.CanvasMixin module, 73 *method*), 184 ginga.rv.plugins.FBrowser module, 120 getTagsByTagpfx() (ginga.canvas.CanvasMixin.CanvasMixin ginga.rv.plugins.Header method), 184 module, 64 getwin\_array() (ginga.ImageView.ImageViewBase ginga.rv.plugins.Histogram module, 98 method), 216 getwin\_buffer() (ginga.ImageView.ImageViewBase ginga.rv.plugins.Info method), 216 module, 63 ginga.canvas.CanvasMixin ginga.rv.plugins.LineProfile module, 183 module, 108 ginga.canvas.CanvasObject ginga.rv.plugins.Log module, 185 module, 81 ginga.canvas.CompoundMixin ginga.rv.plugins.Mosaic module, 189 module, 117 ginga.canvas.coordmap ginga.rv.plugins.MultiDim module,96 module, 192 ginga.canvas.DrawingMixin ginga.rv.plugins.Operations module, 197 module, 70 ginga.canvas.types.layer ginga.rv.plugins.Overlays module, 200 module, 102 ginga.ImageView ginga.rv.plugins.Pan module, 201 module, 62 ginga.rv.main ginga.rv.plugins.Pick module, 226 module,85 ginga.rv.plugins.Blink ginga.rv.plugins.Pipeline module, 107 module, 124 ginga.rv.plugins.Catalogs ginga.rv.plugins.PixTable module, 109 module, 116 ginga.rv.plugins.ChangeHistory ginga.rv.plugins.PlotTable module, 79 module, 123 ginga.rv.plugins.Collage ginga.rv.plugins.Preferences module, 118 module, 111 ginga.rv.plugins.Colorbar ginga.rv.plugins.RC module, 69 module, 73 ginga.rv.plugins.ColorMapPicker ginga.rv.plugins.Ruler module,72 module,94 ginga.rv.plugins.Command ginga.rv.plugins.SAMP module, 82 module, 80 ginga.rv.plugins.Compose ginga.rv.plugins.SaveImage module,83 module, 120 ginga.rv.plugins.Contents ginga.rv.plugins.ScreenShot module, 68 module, 124 ginga.rv.plugins.Crosshair ginga.rv.plugins.Thumbs

is\_compound() (ginga.canvas.CompoundMixin.CompoundMixin

is\_drawing() (ginga.canvas.DrawingMixin.DrawingMixin

is editing() (ginga.canvas.DrawingMixin.DrawingMixin

is\_selected() (ginga.canvas.DrawingMixin.DrawingMixin

(ginga.ImageView.ImageViewBase

(ginga.ImageView.ImageViewBase

method),

*method*), 191

method), 216

method), 199

method), 199

is\_redraw\_pending()

216

is compound()

module, 67 ginga.rv.plugins.Toolbar module, 61 ginga.rv.plugins.TVMark module, 104 ginga.rv.plugins.TVMask module.105 ginga.rv.plugins.WBrowser module, 70 ginga.rv.plugins.WCSAxes module, 103 ginga.rv.plugins.WCSMatch module,77 ginga.rv.plugins.Zoom module, 65 ginga.util.ap\_region module, 237 ginga.util.io.io\_asdf module, 229 ginga.util.wcs module, 233 ginga.util.wcsmod module, 232 ginga\_canvas\_object\_to\_astropy\_region()

# Н

L

method), 199 L lat\_to\_deg() (in module ginga.util.wcs), 237 load asdf() (ginga.util.io.io asdf.ASDFFileHandler method), 231 load\_asdf() (in module ginga.util.io.io\_asdf), 229 load\_asdf\_hdu\_in\_fits() (ginga.util.io.io\_asdf.ASDFFileHandler *method*), 231 load\_file() (ginga.util.io.io\_asdf.ASDFFileHandler method), 231 (in module ginga.util.ap\_region), 238 load\_file() (in module ginga.util.io.io\_asdf), 229 load\_from\_asdf() (in module ginga.util.io.io\_asdf), 229 has\_object()(ginga.canvas.CompoundMixin.CompoundMixin\_dx() (ginga.util.io.io\_asdf.ASDFFileHandler *method*), 191 method), 231 has\_tag() (ginga.canvas.CanvasMixin.CanvasMixin load\_idx\_cont() (ginga.util.io.io\_asdf.ASDFFileHandler method), 184 *method*), 231 hmsStrToDeg() (in module ginga.util.wcs), 234 lon\_to\_deg() (in module ginga.util.wcs), 237 lookup object taq() hmsToDeg() (in module ginga.util.wcs), 234 (ginga.canvas.CanvasMixin.CanvasMixin method), 184 icc\_profile\_cb() (ginga.ImageView.ImageViewBase lower\_object() (ginga.canvas.CompoundMixin method), 191 method), 216 lower\_object\_by\_tag() ImageViewBase (class in ginga.ImageView), 202 inherit\_from() (ginga.canvas.CompoundMixin.CompoundMixin(ginga.canvas.CanvasMixin.CanvasMixin method), 184 *method*), 191 initialize()(ginga.canvas.CanvasObject.CanvasObject@WiseCObject()(ginga.canvas.CompoundMixin.CompoundMixin method), 191 method), 188 initialize() (ginga.canvas.CompoundMixin.CompoundMixinObjectByTag() (ginga.canvas.CanvasMixin.CanvasMixin *method*), 191 method), 184 initialize\_private\_canvas() (ginga.ImageView.ImageViewBase method), M 216main() (ginga.rv.main.ReferenceViewer method), 228 interpolation change cb() (ginga.ImageView.ImageViewBase (ginga.ImageView.ImageViewBase *method*), make\_cursor() method), 217 216 invert cmap() (ginga.ImageView.ImageViewBase make\_timer() (ginga.ImageView.ImageViewBase method), 216 method), 217 is\_compound() (ginga.canvas.CanvasObject.CanvasObjectBase

ginga.canvas.CanvasMixin, 183

method), 188

ginga.canvas.CanvasObject, 185 ginga.canvas.CompoundMixin, 189 ginga.canvas.coordmap, 192 ginga.canvas.DrawingMixin,197 ginga.canvas.types.layer,200 ginga.ImageView, 201 ginga.rv.main, 226 ginga.rv.plugins.Blink, 107 ginga.rv.plugins.Catalogs, 116 ginga.rv.plugins.ChangeHistory,79 ginga.rv.plugins.Collage, 118 ginga.rv.plugins.Colorbar,69 ginga.rv.plugins.ColorMapPicker,72 ginga.rv.plugins.Command,82 ginga.rv.plugins.Compose, 120 ginga.rv.plugins.Contents,68 ginga.rv.plugins.Crosshair,100 ginga.rv.plugins.Cursor,70 ginga.rv.plugins.Cuts,97 ginga.rv.plugins.Downloads, 84 ginga.rv.plugins.Drawing, 119 ginga.rv.plugins.Errors,73 ginga.rv.plugins.FBrowser, 120 ginga.rv.plugins.Header, 64 ginga.rv.plugins.Histogram,98 ginga.rv.plugins.Info,63 ginga.rv.plugins.LineProfile, 108 ginga.rv.plugins.Log,81 ginga.rv.plugins.Mosaic, 117 ginga.rv.plugins.MultiDim,96 ginga.rv.plugins.Operations,70 ginga.rv.plugins.Overlays, 102 ginga.rv.plugins.Pan, 62 ginga.rv.plugins.Pick,85 ginga.rv.plugins.Pipeline, 124 ginga.rv.plugins.PixTable, 109 ginga.rv.plugins.PlotTable, 123 ginga.rv.plugins.Preferences, 111 ginga.rv.plugins.RC,73 ginga.rv.plugins.Ruler,94 ginga.rv.plugins.SAMP,80 ginga.rv.plugins.SaveImage,83 ginga.rv.plugins.ScreenShot, 124 ginga.rv.plugins.Thumbs, 67 ginga.rv.plugins.Toolbar,61 ginga.rv.plugins.TVMark, 104 ginga.rv.plugins.TVMask, 105 ginga.rv.plugins.WBrowser, 70 ginga.rv.plugins.WCSAxes, 103 ginga.rv.plugins.WCSMatch,77 ginga.rv.plugins.Zoom,65 ginga.util.ap\_region, 237 ginga.util.io.io\_asdf, 229 ginga.util.wcs, 233

ginga.util.wcsmod, 232

### Ν

- name (ginga.util.io.io\_asdf.ASDFFileHandler attribute), 230
- NativeMapper (class in ginga.canvas.coordmap), 192

### 0

- offset\_pt() (ginga.canvas.coordmap.WindowMapper method), 193

offset\_to\_window() (ginga.ImageView.ImageViewBase method), 217

OffsetMapper (class in ginga.canvas.coordmap), 196
onscreen\_message()

(ginga.ImageView.ImageViewBase method), 217

- onscreen\_message\_off()
   (ginga.ImageView.ImageViewBase method),
   217

#### Ρ

- pan\_cb() (ginga.ImageView.ImageViewBase method),
  217

<pre>panset_xy() (ginga.ImageView.ImageViewBase method), 217</pre>	(ginga.ImageView.ImageViewBase method), 218
	register_canvas_type()
ginga.canvas.coordmap), 194	(ginga.canvas.DrawingMixin.DrawingMixin
<pre>pick_hover() (ginga.canvas.DrawingMixin.DrawingM</pre>	lixin method), 199
<i>method</i> ), 199	register_canvas_type() (in module
<pre>pick_key() (ginga.canvas.DrawingMixin.DrawingMixi</pre>	
<i>method</i> ), 199	register_canvas_types() (in module
pick_motion() (ginga.canvas.DrawingMixin.Drawing.	
method), 199	register_for_cursor_drawing()
<pre>pick_start() (ginga.canvas.DrawingMixin.DrawingM</pre>	
method), 199	method), 199
<pre>pick_stop() (ginga.canvas.DrawingMixin.DrawingMix method), 199</pre>	(ginga.canvas.CanvasObject.CanvasObjectBase
point_within_line()	method), 188
-	rescale_by() (ginga.canvas.CanvasObject.CanvasObjectBase
method), 188	method), 188
point_within_radius()	rescale_by_factors()
(ginga.canvas.CanvasObject.CanvasObjectBase	(ginga.canvas.CanvasObject.CanvasObjectBase
method), 188	method), 188
position_cursor()	reschedule_redraw()
(ginga.ImageView.ImageViewBase method),	(ginga.ImageView.ImageViewBase method),
218	218
<pre>prepare_image() (ginga.ImageView.ImageViewBase</pre>	reset_limits() (ginga.ImageView.ImageViewBase
<i>method</i> ), 218	<i>method</i> ), 219
<pre>process_drawing()</pre>	restore_cmap() (ginga.ImageView.ImageViewBase
(ginga.canvas.DrawingMixin.DrawingMixin	<i>method</i> ), 219
method), 199	restore_contrast()
R	(ginga.ImageView.ImageViewBase method), 219
<pre>raDegToString() (in module ginga.util.wcs), 235</pre>	rgbmap_cb() (ginga.ImageView.ImageViewBase
<pre>raise_object() (ginga.canvas.CompoundMixin.Comp</pre>	poundMixinmethod), 219
<i>method</i> ), 191	<pre>roll_objects() (ginga.canvas.CompoundMixin.CompoundMixin</pre>
raise_object_by_tag()	method), 192
(ginga.canvas.CanvasMixin.CanvasMixin	rotate() (ginga.canvas.CanvasObject.CanvasObjectBase
method), 184	method), 188
<pre>raiseObject() (ginga.canvas.CompoundMixin.Compo method), 191</pre>	มศักส์ Maxin () (ginga.canvas.CompoundMixin.CompoundMixin method), 192
raiseObjectByTag()	<pre>rotate() (ginga.ImageView.ImageViewBase method),</pre>
(ginga.canvas.CanvasMixin.CanvasMixin	219
<i>method</i> ), 184	rotate_by() (ginga.canvas.CanvasObject.CanvasObjectBase
<pre>recalc_transforms()</pre>	method), 188
(ginga.ImageView.ImageViewBase method),	rotate_by_deg() (ginga.canvas.CanvasObject.CanvasObjectBase
218	method), 188

218 redraw() (ginga.canvas.CanvasMixin.CanvasMixin method), 184

- redraw() (ginga.ImageView.ImageViewBase method), 218
- method), 218

ReferenceViewer (class in ginga.rv.main), 227
refresh\_timer\_cb()

- (ginga.canvas.CanvasMixin.CanvasMixin rotate\_deg() (ginga.canvas.CanvasObject.CanvasObjectBase od), 184 method), 188

<pre>rotate_pt() (ginga.canvas.coordmap.PercentageMapp</pre>	<pre>perset_autocenter() (ginga.ImageView.ImageViewBase method), 220</pre>
<pre>rotate_pt() (ginga.canvas.coordmap.WCSMapper</pre>	(ginga.ImageView.ImageViewBase method),
<pre>rotate_pt() (ginga.canvas.coordmap.WindowMapper</pre>	<pre>set_autocuts() (ginga.ImageView.ImageViewBase</pre>
<pre>rotation_change_cb()     (ginga.ImageView.ImageViewBase method),     219</pre>	<pre>method), 220 set_background() (ginga.ImageView.ImageViewBase method), 220</pre>
S	set_bg() (ginga.ImageView.ImageViewBase method), 220
<pre>save_plain_image_as_file()     (ginga.ImageView.ImageViewBase method),     219</pre>	<pre>set_calg() (ginga.ImageView.ImageViewBase method), 220 set_canvas() (ginga.ImageView.ImageViewBase</pre>
<pre>save_profile() (ginga.ImageView.ImageViewBase method), 219</pre>	<pre>method), 220 set_cmap() (ginga.ImageView.ImageViewBase</pre>
<pre>save_rgb_image_as_file()     (ginga.ImageView.ImageViewBase method),     219</pre>	<pre>method), 221 set_color_algorithm()     (ginga.ImageView.ImageViewBase method),</pre>
<pre>scale_and_shift_cmap()     (ginga.ImageView.ImageViewBase method),     219</pre>	221 set_color_map() (ginga.ImageView.ImageViewBase method), 221
<pre>scale_by() (ginga.canvas.CanvasObject.CanvasObject method), 188</pre>	Baset_coordmap() (ginga.ImageView.ImageViewBase method), 221
<pre>scale_by_factors()     (ginga.canvas.CanvasObject.CanvasObjectBase     method), 189</pre>	<pre>set_cursor() (ginga.ImageView.ImageViewBase method), 221 set_data() (ginga.canvas.CanvasObject.CanvasObjectBase</pre>
<pre>scale_by_factors()     (ginga.canvas.CompoundMixin.CompoundMixin     method), 192</pre>	<i>method</i> ), 189
<pre>scale_cb() (ginga.ImageView.ImageViewBase method), 220</pre>	(ginga.canvas.CanvasObject.CanvasObjectBase
<pre>scale_font() (ginga.canvas.CanvasObject.CanvasObj method), 189</pre>	<pre>set_dataobj() (ginga.ImageView.ImageViewBase</pre>
<pre>scale_to() (ginga.ImageView.ImageViewBase</pre>	<pre>method), 221 set_desired_size() </pre>
<pre>select_add() (ginga.canvas.DrawingMixin.DrawingM method), 199</pre>	221
<pre>select_contains()     (ginga.canvas.CanvasObject.CanvasObjectBase     method), 189</pre>	<pre>set_draw_mode() (ginga.canvas.DrawingMixin.DrawingMixin</pre>
<pre>select_contains_pt()     (ginga.canvas.CanvasObject.CanvasObjectBase</pre>	<pre>method), 200 set_drawtype() (ginga.canvas.DrawingMixin.DrawingMixin</pre>
<pre>method), 189 select_contains_pt()     (ginga.canvas.CompoundMixin.CompoundMixin</pre>	
<pre>method), 192 select_items_at()     (ginga.canvas.CompoundMixin.CompoundMixin</pre>	222 set_fg() (ginga.ImageView.ImageViewBase method), 222
<pre>method), 192 select_remove() (ginga.canvas.DrawingMixin.Draw</pre>	<pre>set_foreground() (ginga.ImageView.ImageViewBase</pre>
<pre>method), 199 set_attr_all() (ginga.canvas.CompoundMixin.Comp     method), 192</pre>	

method),

method),

(ginga.ImageView.ImageViewBase

(ginga.ImageView.ImageViewBase

224

224

method). 224

method), 224

method), 222 set\_intensity\_map() (ginga.ImageView.ImageViewBase *method*), show mode indicator() 2.2.2 set limits() (ginga.ImageView.ImageViewBase method), 222 show pan mark() (ginga.ImageView.ImageViewBase (ginga.ImageView.ImageViewBase set name() method), 222 simple\_wcs() (in module ginga.util.wcs), 236 start\_refresh() (ginga.ImageView.ImageViewBase set\_onscreen\_message() (ginga.ImageView.ImageViewBase method), stop\_refresh() (ginga.ImageView.ImageViewBase 222 (ginga.ImageView.ImageViewBase set\_pan() method), 222 set\_point\_by\_index() (ginga.canvas.CanvasObject.CanvasObjectBase method), 189 set\_redraw\_lag() (ginga.ImageView.ImageViewBase method), 223 set\_refresh\_rate() (ginga.ImageView.ImageViewBase method), 223 set\_renderer() (ginga.ImageView.ImageViewBase method), 223 (ginga.ImageView.ImageViewBase set\_rgbmap() Т method), 223 set\_scale() (ginga.ImageView.ImageViewBase method), 223 set\_scale\_base\_xy() (ginga.ImageView.ImageViewBase method), 223 set\_scale\_limits() (ginga.ImageView.ImageViewBase method). 223 set\_surface() (ginga.canvas.DrawingMixin.DrawingMixindata() method), 200 set window size() (ginga.ImageView.ImageViewBase *method*), 223 set\_zoom\_algorithm() (ginga.ImageView.ImageViewBase method), 224 set\_zoomrate() (ginga.ImageView.ImageViewBase method), 224 setAttrAll() (ginga.canvas.CompoundMixin.CompoundMixin method), 192 setSurface() (ginga.canvas.DrawingMixin.DrawingMixin method), 199 setup\_edit() (ginga.canvas.CanvasObject.CanvasObjectBase method), 189 (ginga.ImageView.ImageViewBase shift\_cmap() method), 224 show\_color\_bar() (ginga.ImageView.ImageViewBase method), 224 show\_focus\_indicator()

method), 224 subcanvas\_updated\_cb() (ginga.canvas.CanvasMixin.CanvasMixin method), 184 swap\_objects() (ginga.canvas.CompoundMixin.CompoundMixin method), 192 swapxy() (ginga.canvas.CanvasObject.CanvasObjectBase method), 189 switch cursor() (ginga.ImageView.ImageViewBase method), 224

sync\_state() (ginga.canvas.CanvasObject.CanvasObjectBase method), 189

take\_focus() (ginga.ImageView.ImageViewBase method), 224 to data() (ginga.canvas.coordmap.CartesianMapper method), 195 to data() (ginga.canvas.coordmap.DataMapper method), 195 (ginga.canvas.coordmap.NativeMapper to\_data() method), 193 (ginga.canvas.coordmap.OffsetMapper method), 196 to\_data() (ginga.canvas.coordmap.PercentageMapper method), 194 to\_data() (ginga.canvas.coordmap.WCSMapper method), 197 (ginga.canvas.coordmap.WindowMapper to\_data() method), 193 trans\_coeff() (in module ginga.util.wcs), 235 transform() (ginga.ImageView.ImageViewBase method), 224 transform cb() (ginga.ImageView.ImageViewBase method), 225 update\_canvas() (ginga.canvas.CanvasMixin.CanvasMixin method), 185 update\_image() (ginga.ImageView.ImageViewBase method), 225

update\_widget() (ginga.ImageView.ImageViewBase method), 225

use\_coordmap() (ginga.canvas.CanvasObject.CanvasObjectBase method), 189

# V

## W

```
WCSMapper (class in ginga.canvas.coordmap), 196
window_has_origin_upper()
    (ginga.ImageView.ImageViewBase method),
    225
window_to_offset()
    (ginga.ImageView.ImageViewBase method),
    225
WindowMapper (class in ginga.canvas.coordmap), 193
within_line() (ginga.canvas.CanvasObject.CanvasObjectBase
    method), 189
within_radius() (ginga.canvas.CanvasObject.CanvasObjectBase
    method), 189
```

# Ζ

zoom\_fit() (ginga.ImageView.ImageViewBase method), 225 zoom\_in() (ginga.ImageView.ImageViewBase method), 225 (ginga.ImageView.ImageViewBase zoom\_out() method), 225 (ginga.ImageView.ImageViewBase zoom\_to() method), 225 zoomsetting\_change\_cb() (ginga.ImageView.ImageViewBase method), 225